

ELECTION WORKER GUIDE

NOVEMBER 3, 2026 GENERAL ELECTION



REVISION: VC20260923-05



ALAMEDA COUNTY
Registrar of Voters

1225 FALLON STREET, RM. G-1
OAKLAND, CA 94612
(510) 272-6973
acvote.alamedacountyca.gov

TABLE OF CONTENTS

WHO TO CALL	1
WELCOME	
ELECTION WORKER ETIQUETTE	2
SERVING THE COMMUNITY	
VOTER BILL OF RIGHTS	3
VOTER ASSISTANCE: ACCESSIBILITY ASSISTANCE	3
INTRODUCTION	
WHAT'S NEW?	7
NEW TO THIS ELECTION	8-11
ELECTION OBSERVERS	12
TRUSTED ELECTION INFORMATION	12
VOTE CENTER STAFF – VOTE CENTER HOURS	13
DELIVERED TO THE VOTE CENTER	14
HANDS-ON TRAINING	15
PRE-ELECTION RESPONSIBILITIES: CAPTAIN	
CELL PHONE OPERATING INSTRUCTIONS	19
TASK 1 CONFIRM ACCESS TO THE VOTE CENTER	20
TASK 2 CONTACT ELECTION WORKERS	20
PRE-ELECTION RESPONSIBILITIES: FRIDAY SETUP	
TASK 1 VOTE CENTER NUMBER	23
TASK 2 LOCATE SUPPLIES	23
TASK 3 CRADLEPOINT ROUTER SET UP	24-25
TASK 4 SYNCHRONIZING POLL PADS	26-27
TASK 5 POWER OFF EQUIPMENT	28-30
TASK 6 INDOOR SETUP	31
TASK 7 SET UP OFFICIAL TABLE	32
OFFICIAL TABLE DIAGRAM: FRIDAY SETUP	32-33
TASK 8 LABEL COLORED BAGS	33
TASK 9 SET UP VOTING BOOTHS	34-35
TASK 10 SET UP ACCESSIBLE VOTING BOOTH	36
TASK 11 SET UP TOUCHSCREEN VOTING BOOTH	37
TASK 12 POST INSIDE SIGNS	38-41
OPENING	
VOTING MUST START AT SCHEDULED TIME	45
TASK 1 GIVE OUT BADGES	45
TASK 2 CRADLEPOINT ROUTER SET UP	46-48
TASK 3 POLL PAD SET UP	49-52
TASK 4 BALLOT ON DEMAND PRINTING SET UP	53-56

TABLE OF CONTENTS

OPENING: JUDGE

TASK 5	VIG ON DEMAND SET UP	57-59
	OFFICIAL TABLE DIAGRAM	60-61
TASK 6	SET UP TURQUOISE OFFICIAL BALLOTS BAG	62-63
TASK 7	SET UP BALLOT MARKING TOUCHSCREEN	64
	SEAL VERIFICATION FORM: 4 DAYS – 11 DAYS	65-66
TASK 8	SEAL VERIFICATION FORM	67-68
TASK 9	POST OUTSIDE SIGNS	68-70
TASK 10	ADMINISTER THE OATH OF OFFICE	71
TASK 11	CHECK THE FOLLOWING	72
TASK 12	ANNOUNCE OPENING OF THE POLLS	72

BALLOT MARKING TOUCHSCREEN: SETUP

	SETTING UP BALLOT MARKING TOUCHSCREEN	75
	SETTING UP PRINTER	76
	POWERING ON	77-79
	OPENING THE POLLS ON THE BALLOT MARKING TOUCHSCREEN	80-82

ELECTION DAY

	1ST VOTER PROCEDURE	85
	THE OFFICIAL TABLE: INTRODUCTION	85
	BREAK SCHEDULE	86
	ETIQUETTE REMINDER	87
	LINE MANAGEMENT	88

OFFICIAL TABLE: POLL PAD OPERATOR

TASK 1	GREET VOTER	91
TASK 2	PROCESSING VOTER	92-94
POLL PAD SCENARIOS		
	VOTE BY MAIL VOTERS	95-98
	VOTER ASSISTANCE REQUIRED	99
	YOUTH VOTERS	100
	VOTER ID REQUIRED – VOTER INACTIVE	101
	VOTER ALREADY VOTED – VOTER BALLOT RECEIVED	102
	VOTER NOT FOUND – CONFIDENTIAL VOTER	103
	UPDATE VOTER ADDRESS/PARTY	104-105
	CONDITIONAL VOTER	106-108
	PROVISIONAL VOTER	109-110
	VOTER SUBMITS A VOTER REGISTRATION FORM	110
	LANGUAGE HOTLINES	111
	VIDEO CALLING	112
POLL PAD TROUBLESHOOTING		113-116

OFFICIAL TABLE: BALLOT ON DEMAND OPERATOR

TASK 1	BALLOT ON DEMAND PRINTING	119-120
TASK 2	FINISHED BALLOT CARD LOG	120
TASK 3	BALLOT TO VOTER	121

BALLOT ON DEMAND SCENARIOS

VOTER INFORMATION GUIDE ON DEMAND PRINTING	122
FACSIMILE REFERENCE BALLOT PRINTING	123
OFFICIAL VOTE CENTER BALLOTS	124-125
OFFICIAL POLL BALLOTS RUNNING LOW	125
BOD PRINTER JAM	126
SPOILING PAPER BALLOT	126-127
SPOILING TOUCHSCREEN BALLOT	127
DAMAGE BALLOT INVENTORY CONTROL LOG	128
MOBILE BALLOT PRINTER HOUSING ACCESS LOG	129
BALLOT PRINTING SYSTEM BALLOT IMAGES DELETION LOG	129

OFFICIAL TABLE: DEMONSTRATION OFFICER

TASK 1	ASSISTING VOTER	133
TASK 2	DEPOSITING BALLOT	133-135
TASK 3	VOTERS EXITING	135

DEMONSTRATION OFFICER SCENARIOS

ASSISTANCE MARKING THE BALLOT	136
VOTER LEAVES BEFORE CASTING BALLOT	136
BALLOT MARKING TOUCHSCREEN PAPER REFILL	136

VOTERS WITH DISABILITIES

DISABILITY SENSITIVITY AT THE POLLS	139-140
ACCESSIBLE CURBSIDE VOTING	141
SUPPLIES FOR VOTERS WITH DISABILITIES	142

BALLOT MARKING TOUCHSCREEN: VOTING

BALLOT ACTIVATION	145
ACCESSIBLE VOTING ACTIVATION	146
AUDIO TACTILE INTERFACE (ATI)	147
CANCELING ACTIVATION	147
TROUBLESHOOTING	148

ELECTION SCENARIOS

ELECTIONEERING	151
VOTER INTIMIDATION	151
MEDIA AT THE VOTE CENTER	152

TABLE OF CONTENTS

ELECTION SCENARIOS

CAMERAS AT THE VOTE CENTER	152
DE-ESCALATION	153
DISTURBANCE AT THE VOTE CENTER	154
ARTIFICIAL INTELLIGENCE CAPABILITIES & CONSIDERATIONS	154
CHALLENGING A VOTER’S RIGHTS	154
REPORTING VOTER FRAUD	154
LAW ENFORCEMENT OFFICERS AT THE VOTE CENTER	154
EMERGENCY SITUATIONS	155
SEE SOMETHING, SAY SOMETHING	155

ROVER PROCEDURE

AFTERNOON PICK UP	
ROVER PREPARATION	159
YELLOW VOTE BY MAIL BALLOTS TROLLEY #1	159
TURQUOISE OFFICIAL BALLOTS BAG	160-161

CLOSING

SUPPLY CHAIN: OPENING	165
TASK 1 ANNOUNCE CLOSING OF THE POLLS	166
TASK 2 CLOSING ROVER PICK UP	166-168
TASK 3 SEAL OFFICIAL VOTE CENTER BALLOTS	169
TASK 4 CLOSING POLL PAD	170-171
TASK 5 PACK CRADLEPOINT ROUTER	172
TASK 6 SHUT DOWN BALLOT ON DEMAND	173
TASK 7 SHUT DOWN VIG ON DEMAND	174-175
TASK 8 CLOSING BALLOT MARKING TOUCHSCREENS	176
TASK 9 PACK ITEMS IN COLORED BAGS	176
TASK 10 PACK ITEMS IN LIME BAG	177
TASK 11 PACK ITEMS ON OFFICIAL TABLE	178
TASK 12 PACK OPENING POLLS SUPPLY BOX	178-179
TASK 13 PACK ELECTRICAL SUPPLY BOX	180
TASK 14 PACK CAPTAIN SUPPLY BOX	181
TASK 15 STORE & SEAL SUPPLIES	182
TASK 16 DISMANTLE BLUE VOTING BOOTHS	183-184
TASK 17 DISMANTLE TOUCHSCREEN VOTING BOOTHS	185
TASK 18 PACK LARGE SIGNAGE	186

BALLOT MARKING TOUCHSCREEN: CLOSING

CLOSING POLLS	189-190
POWERING OFF	191

BALLOT MARKING TOUCHSCREEN: CLOSING

DISASSEMBLING PRINTER	192
DISASSEMBLING TOUCHSCREEN	193

MY ELECTION WORKER PROFILE 194

ELECTION WORKERS QUESTIONS 194

BILINGUAL ELECTION WORKERS 194

FOR URGENT ELECTION WORKER QUESTIONS:

- **Election Worker Hotline:** (510) 835-7205 (Phone line opens the Friday before Early Voting begins)


HOTLINE HOURS:

- **Friday before Early Voting:** 8:30 AM – 5 PM
- **Saturday – Monday, during Early Voting:** 8 AM – 6 PM
- **Tuesday, Election Day:** 6 AM – After all Vote Centers close

Video Calling is available. Solve issues quickly and ask to start a video call when you call the Election Worker Hotline.

FOR VOTER QUESTIONS:

- **Alameda County Registrar of Voters:** (510) 272-6973
- **If you suspect fraud, call the California Secretary of State:** (916) 657-2166



ELECTION WORKER ETIQUETTE

ATTENTION ALL ELECTION WORKERS!

The following guidelines are intended to help you on Election Day and help us maintain a good working relationship with all of our Vote Center organizers.

PLEASE REMEMBER: The manner in which you communicate with the Vote Center organizers directly affects whether or not we are able to continue using a facility. Please show consideration for the person(s) allowing us to use their facility. Please keep the following suggestions in mind on Election Day when you are working at the Vote Center.

- Election Workers are not allowed to bring children to the Vote Center.
- We are guests in the Vote Center facility. The Captain should familiarize themselves with the rules. Use tape carefully on the walls or woodwork so that you do not permanently damage the facility. If in doubt, ask first.
- Be polite to the other occupants sharing the space. If major problems occur, call the Registrar of Voters' Office.
- Bilingual Election Workers are present in order to assist the language communities. The Bilingual Election Workers are placed in each Vote Center based on the number of language Voters in that area. Any missing Bilingual Election Worker must be replaced.
- Do not move large furniture without permission.
- The Vote Center organizers are not required to give Election Workers access to bathroom facilities, telephones, and kitchens. If they are offered, please keep them neat. If they are not available, please make other arrangements.
- All Election Workers are an extension of the Registrar of Voters' Office. The manner in which you perform your duties is a direct reflection of our office.
- Election Workers must be dressed in appropriate business casual attire.
- Use of cell phones while serving is STRICTLY PROHIBITED. Please use while on break only.
- Discussion about the election or any political topic is STRICTLY PROHIBITED. If this becomes an issue, call the Registrar of Voters' Office.
- Eating at the Voting area and the Official table is STRICTLY PROHIBITED.

NOTE:

- Cleaners from vendor companies, and any other non-election workers who may be present in the facility, must not be asked to assist with any election duties. This includes moving voting equipment, handling election materials, or participating in voter check-in. Only trained Election Workers may perform election operations.
- Poll Pads must only be used to look up voters who are physically present at the Vote Center to vote. Election Workers must not use Poll Pads to search for neighbors, friends, or any individuals who are not currently checking in to vote.
- All Election Workers must follow the Election Worker Guide to protect voter privacy and maintain secure, professional operations.
- Personal cell phones and tablets may not be used at the Official Table(s) or Demonstration Officer table.
- Captains and Assistant Captains should remind Election Workers of proper etiquette and Poll Pad procedures throughout the day.

THANK YOU FOR SERVING AS AN ELECTION WORKER!

VOTER BILL OF RIGHTS

The Help America Vote Act (HAVA) requires a Voter Bill of Rights to be posted both inside and outside the Vote Center. The Alameda County Registrar of Voters is required to post English, Chinese, Spanish, Tagalog, and Vietnamese versions of this Bill. All Vote Centers will be required to post additional versions in Bengali, Burmese, Hindi, Japanese, Khmer, Korean, Laotian, Malay, Mien, Mongolian, Punjabi, Telugu, and Urdu. It is your duty to ensure these rights are extended to all Voters.

1. You have the right to cast a Ballot if you are a valid Registered Voter. You are eligible to vote if you are:
 - a U.S. citizen living in California
 - at least 18 years old
 - registered where you currently living
 - not currently serving a state or federal prison term for the conviction of a felony, and
 - not currently found mentally incompetent to vote by a court
2. You have the right to cast a Conditional/Provisional Ballot if your name is not listed on the voting rolls.
3. You have the right to cast a Ballot if you are present and in line at the Vote Center prior to the close of the polls.
4. You have the right to cast a secret Ballot, free from intimidation.
5. You have the right to receive a new Ballot if, prior to casting your Ballot, you believe you made a mistake.
6. You have the right to receive assistance in casting your Ballot, if you are unable to vote without assistance.
7. You have the right to return a completed Vote by Mail Ballot to any 24-hour Ballot Drop Box or Vote Center in the county.
8. You have the right to Election Materials in another language, if there are sufficient residents in your precinct to warrant production.
9. You have the right to ask questions about Election procedures and observe the Election process.
10. You have the right to report any illegal or fraudulent activity to a local Elections Official or to the Secretary of State's Office.

VOTER ASSISTANCE: ACCESSIBILITY ASSISTANCE

The **Americans with Disabilities Act (ADA)** and **Help America Vote Act (HAVA)** require that assistance, equipment, and voting machines be provided to make the voting process available to Voters with a range of needs. For more information on working with Voters requiring assistance, refer to the ***Voters with Disabilities: Sensitivity at the Polls*** (pg. 139) of the Election Worker Guide.

INTRODUCTION

INTRODUCTION

VOTE BY MAIL:

- Every Registered Voter will receive a Vote by Mail Ballot for this Election
- Vote by Mail Replacement Envelope will be available



VOTE CENTERS:

- All Vote Centers will be open for three (3) days of Early Voting as well as on Election Day. Twenty (20) select locations will be open for ten (10) days of Early Voting and on Election Day
- Available to all Voters that want to vote or drop off their Vote by Mail Ballot, as well as Voters that need assistance, or if damaged or lost Vote by Mail Ballots
- No need to surrender Vote by Mail materials to vote
- Voting hours are 9 am to 5 pm during days for Early Voting and 7 am to 8 pm on Election Day



NEW VOTING EQUIPMENT:

- Ballot Marking Touchscreens
 - Marks and prints Official Ballot. Does not cast/record votes
- No Scanner
- Voter Information Guide On Demand Printing available
- Electronic Poll Pad replaces Roster Index
- Ballot On Demand (BOD) Printing Cart



CONDITIONAL PROVISIONAL REGISTRATION FORM:

- Register and vote the same day
- Conditional Voter Registration and Provisional use one combined envelope called Conditional/Provisional Ballot/Voter Registration Form



NEW TO THIS ELECTION

RANKED-CHOICE VOTING (RCV)

Ranked-Choice Voting allows voters to rank candidates, in order of preference, when marking their ballots. **Ranked-Choice Voting** eliminates the need for run-off elections. Voters in the cities of **Albany, Berkeley and Oakland** will receive multiple ballot cards, including a **Ranked-Choice Voting** ballot card. Visit **ACVOTE.AlamedaCountyCA.gov/rcv** for more information.

RANKED-CHOICE VOTING (RCV) INSTRUCTIONS

	1st Choice	2nd Choice	3rd Choice	4th Choice	5th Choice
ROBIN	☐	☐	☐	☐	☒
BRUCE	☒	☐	☐	☐	☐
ARTHUR	☐	☐	☒	☐	☐
LINH	☐	☒	☐	☐	☐
EMMA	☐	☐	☐	☐	☐
WRITE-IN <i>Georgio</i>	☐	☐	☐	☒	☐

How to Vote

To vote on the contest, rank the candidates by completely filling in ovals from left to right in order of your preference, up to five choices, or in Oakland as many as you want.

- In the **1st column**, fill in the oval for your **1st choice**
- In the **2nd column**, fill in the oval for your **2nd choice**
- Fill in the ovals for your remaining choices in the **3rd, 4th, and so on...**

1st Choice	2nd Choice	3rd Choice	4th Choice
☐	☒	☐	☐
☒	☐	☐	☐
☐	☐	☐	☒
☐	☐	☒	☐

Rank candidates in your order of choice.

1st Choice	2nd Choice	3rd Choice	4th Choice
☐	☐	☐	☐
☒	☐	☐	☐
☒	☐	☐	☐
☐	☐	☐	☐

Mark no more than 1 oval in a column. We will not be able to count either vote.


1st Choice	2nd Choice	3rd Choice	4th Choice
☐	☐	☐	☐
☒	☒	☒	☒
☐	☐	☐	☐
☐	☐	☐	☐

Mark no more than 1 oval in a row. We will only be able to count your first ranking. All others will not count.

HOW RANKED-CHOICE VOTING CONTESTS ARE COUNTED – BERKELEY & OAKLAND

We begin by counting all first-choice votes.


If any candidate received a majority of votes (50%+1), that candidate wins.



What if no candidate receives a majority of first-choice votes?


We eliminate the candidate with the lowest number of votes.

If you voted for the eliminated candidate, your vote moves to your second choice.



The candidate in last place (Candidate A) is eliminated. Voters who chose Candidate A as their first choice will have their vote moved to their second choice.

We count the votes again. If a candidate now has a majority of votes, that candidate wins.



The votes are counted again. Candidate C is now the winner because Candidate C has a majority of votes.


NEW TO THIS ELECTION

HOW RANKED-CHOICE VOTING CONTESTS ARE COUNTED – ALBANY

1

Everyone's First Choice Votes Are Counted


Votes are counted in rounds that repeat until all seats are filled.



2

Is There a Winner?

- **City Council (2 seats):**
A candidate must gain more than 1/3 of votes to win.
- **Board of Education (4 seats):**
A candidate must gain more than 1/5 of votes to win.



3

If No Candidates Secure Enough Votes in a Round

The candidate with the fewest votes is eliminated. If that candidate was your 1st choice, your vote automatically moves to your next ranked choice.



4

If Your Candidate Wins With Extra Votes

A portion of your vote can help support your next choice.



For more information about Ranked-Choice Voting in Albany, contact:
Albany City Clerk | (510) 528-5710 | CityClerk@AlbanyCA.gov

YOUTH VOTING FOR ALBANY, BERKELEY, & OAKLAND

Youth Voters can now vote in Albany, Berkeley, and Oakland in School Board Elections.

In November 2016, Berkeley voters approved Measure Y1 and in November 2020, Oakland voters approved Measure QQ allowing 16 and 17-year-olds to vote only in School Board Elections.

**NOVEMBER 3, 2026, GENERAL ELECTION**

Every eligible pre-registered voter will receive a Vote by Mail Ballot in the mail.

**WHEN VOTER TURNS 18**

The voter's voter registration will automatically become active on their 18th birthday. They will no longer be a pre-registered youth voter and will be eligible to vote on federal, statewide and local contests.

**IN-PERSON VOTING**

Youth Voters voting in Albany, Berkeley, and Oakland in School Board Elections can vote in-person at any Vote Center throughout Alameda County or the Alameda County Registrar of Voters' Office, 1225 Fallon Street, Room G-1, Oakland, CA 94612 (public entrance on 12th Street).

Voter Information Guides and Facsimile Ballots for Youth Voting are available upon request at any Vote Center throughout Alameda County or at the Alameda County Registrar of Voters' Office.

ELECTION OBSERVERS

As in all Elections, Observers must be accommodated. Space should be made for observation. Observers are members of the public engaged in observing activities at the Vote Center. Observers must check in with the Vote Center Captain to receive an Observer identification badge. Observers should also be given a copy of the Election Observer Rights and Responsibilities. Department of Justice Observers will identify themselves; they are allowed to touch Voting Equipment and Documents. Observers will need to be able to view the Vote Center process and may periodically ask to look at the voting equipment.

If an Observer refuses to respect the rules, the Captain must notify the Election Worker Hotline, (510) 835-7205, immediately.

Total number of Observers is subject to available space at the Vote Center.

GUIDELINES FOR OBSERVERS

Observers are responsible for:

- Checking in with the Vote Center Captain at each Vote Center.
- Wearing the identification badge provided by the Election Workers after checking in. The identification badge must remain worn and visible at all times.
- Following the established Election Observer Rights and Responsibilities and instructions of the election officials.

Observers are allowed to:

- Observe activity at the Vote Center throughout the day, including Opening and Closing procedures.
- Ask questions, and/or allowed to be directed to the Registrar of Voters, (510) 272-6933, for Election process related questions.
- Visually inspect the integrity of external Security Seals used to secure Voting Equipment with an Election Worker escorting them.
 - Such inspection can only be done when it does not interfere with the privacy of any Voter.

Observers are NOT allowed to:

- Talk to Voters within one hundred (100) feet of the room where voting is taking place.
- Interfere with a Voter's right to privacy.
- Talk with voters who are voting.
- Stop a voter from voting.
- Sit at any table.
- Create distractions or disturbances.
- Campaign or electioneer.
- Talk to Election Workers while they are assisting a voter.
- Modify an election procedure.
- Use cell phones, pagers, cameras, and other audio or video equipment or electronic devices.

TRUSTED ELECTION INFORMATION

The Alameda County Registrar of Voters' Office is committed to ensuring that elections are free, fair, safe, secure, accurate, and accessible. Misinformation, intentional or otherwise, continues to confuse voters and sow distrust in the electoral process.

If voters receive a call or text message with inaccurate information about their voter registration, they can verify their registration status at ACVOTE.AlamedaCountyCA.gov/mvp or contact our office at **1 (800) 834-6454**.

VOTE CENTER STAFF

WHAT MAKES UP A VOTE CENTER BOARD?

Persons appointed to serve as Election Workers I* and Election Workers II** for the Vote Center (CEC § 12301).

*Election Workers I work at 4-day Vote Centers
 **Election Workers II work at 11-day Vote Centers



CAPTAIN

- Captain is an Election Worker that leads Vote Center.



ASSISTANT CAPTAIN

- Assistant Captain is an Election Worker that helps lead Vote Center.



JUDGES

- Judges are Election Workers that assist Captain and Assistant Captain with the Vote Center.


VOTE CENTER HOURS

VOTING HOURS

EARLY VOTING: 9 AM to 5 PM
ELECTION DAY: 7 AM to 8 PM

STAFF HOURS


EARLY VOTING: 8 AM (7:30 AM, first day of Early Voting) until after Rover Pickup and Vote Center closing
ELECTION DAY: 6 AM until after Rover Pickup and Vote Center closing



SUPPLY DELIVERY BOXES



OFFICIAL BALLOTS DELIVERY CARTS



BALLOT ON DEMAND PRINTING CARTS

NOTE: All delivered materials must have matching labels with the Vote Center (location) number.

To schedule an appointment, contact: (510) 272-6971



ARENA CENTER
7001 Oakport Street
Oakland, CA 94621

PRE-ELECTION RESPONSIBILITIES CAPTAIN

PRE-ELECTION RESPONSIBILITIES CAPTAIN

POWER ON

1. Before Early Voting and Election Day, **PRESS & HOLD** the power button located on the right side for a few seconds until the Samsung logo appears and the phone vibrates.
2. **RELEASE** the power button and wait for the device to fully boot.

NOTE: Each Vote Center will receive two (2) cell phones labeled “**VOTE CENTER VC.###A**” and “**VOTE CENTER VC.###B**”. Both phone labels will correspond to the assigned Vote Center number.

Power on both cell phones upon receipt and make sure they are fully charged and working. Make sure that you have enough battery life to boot up your phone. If you are not able to turn it on, charge it for 5 MINUTES before attempting again.



CLOSING

1. **POWER OFF** cell phones after Closing Procedures have been completed, including Rover Pick Up.
2. **PLACE CELL PHONE POUCHES**, along with the Poll Worker Card, inside the Captain Supply Box.

NOTE: Cell phones must always remain inside the Vote Center and must not be taken home or removed from the Vote Center during breaks or lunch.

TASK 1 CONFIRM ACCESS TO THE VOTE CENTER

1. **CONTACT** the person in charge of the Vote Center location a week prior to confirm that it is available for set-up starting the Friday before Early Voting at 2:00 PM.

TASK 2 CONTACT ELECTION WORKERS

1. **CONFIRM** all listed Election Workers' attendance for Early Voting.
2. **REMIND** all listed Election Workers the time and location to report for duty.
3. **COORDINATE** with the Assistant Captain and up to two (2) Election Workers to assist with setup of the Vote Center at the arranged time on the Friday before Early Voting with the Vote Center contact person.

PRE-ELECTION RESPONSIBILITIES FRIDAY SETUP


PRE-ELECTION RESPONSIBILITIES FRIDAY SETUP

TASK 1 VOTE CENTER NUMBER

- CHECK** that the Vote Center Number on all delivered materials matches your assigned Vote Center before setting up:
 - Supply Delivery Boxes
 - Official Ballots Delivery Carts
 - Ballot On Demand Printing Carts

NOTE: If the Vote Center Number is incorrect on any of the items, **CONTACT** the Election Worker Hotline at (510) 835-7205.

TASK 2 LOCATE SUPPLIES



The Supply Chain is located in the Captain Supply Box. To locate the Captain Supply Box, read the list of items found on each Official Ballots Delivery Cart.

- USE** the Supply Chain diagram to assist in finding where supplies are located.

If any supplies are missing, contact the Election Worker Hotline at (510) 835-7205.

NOTE: This page is a representation of the Supply Chain document, which is located in the Captain Supply Box.


TASK 3 CRADLEPOINT ROUTER SET UP

SUPPLIES LOCATED IN THE OFFICIAL BALLOTS DELIVERY CART



1. The Cradlepoint Internet Routers are located within a protective case. **REMOVE** one set of contents from the Cradlepoint case and its protective foam packaging. **PLACE** it where it would have the best signal, also within a few feet of the Poll Pad. **PLACE** the foam and case aside.

NOTE: One (1) Cradlepoint set contains the router, two (2) flat antennas, and one (1) power cable.




2. **SCREW** the two (2) Cradlepoint antennas into the ports. **BEND** them (at the joints) so they are spread out for the best connectivity. **DO NOT SCREW** any into the center port.



3. **CONNECT** the power cord to the back of the Cradlepoint, **CONNECT** the power cord to a power source, and then **FLIP** the power switch, located beside the connection, upward to turn it on.


4. **Full connectivity may take up to 15 minutes after Cradlepoint is powered on.** The blue lights on the front determine the signal strength. Blue, orange, and green must be on for full connectivity.

If any of the lights are not on, UNPLUG AND PLUG back in to reconnect. **CALL** Election Worker Hotline to assess.



TASK 4 SYNCHRONIZING POLL PADS

SUPPLIES LOCATED IN THE OFFICIAL BALLOTS DELIVERY CART




1. **RETRIEVE** Poll Pad from the carrying case lid. **PLACE** case aside.



2. **PRESS** the power button on the top right edge of the unit until you see the Apple logo. **POWER ON** all Poll Pads to begin the synchronization process.




3. **PRESS** the application icon at the bottom of the screen.



4. CHECK THE FOLLOWING:

- Screen says "Alameda County"
- Election name and date
- **IMPORTANT:** Verify the Vote Center location is correct
- Check-in Count = 0
- Battery life is close to full and/or being charged



- The Poll Pad will automatically connect to the Cradlepoint Router's WiFi network. **MAKE SURE** both the cloud icon is green and the Poll Pad is connected to the WiFi. **PRESS** the cloud icon to confirm that the synchronization is finished.

TASK 5 POWER OFF EQUIPMENT



1. After the Poll Pads have finished syncing, on the back of the Cradlepoint, **FLIP** the power switch downward to the OFF position. **REMOVE** power cord from the back of the Cradlepoint and the power source.

NOTE: **PRESS** on the bottom tab of the connector while removing the power cord (as seen in the photo).






2. **UNSCREW** the antennas from the back of the Cradlepoint. **RETRIEVE** the Cradlepoint box and **PLACE** the antennas and power cord in the box.




3. **PLACE** the Cradlepoint box back in the Official Ballots Delivery Cart.

TASK 5 POWER OFF EQUIPMENT



4. **TURN OFF** Poll Pad by holding the power button until the screen indicates to "slide to power off" and **FOLLOW** on-screen instructions. **DISCONNECT** the charger from the Poll Pad.




5. **PLACE** the Poll Pad inside the lid of the carrying case and **USE** the velcro strap to secure. **CLOSE** the lid and **SECURE**.
6. **PLACE** Poll Pad case in the Official Ballots Delivery Cart.
7. **SECURE** any opened Official Ballots Delivery Carts with White Security Seals.

TASK 6 INDOOR SETUP

CREATE A CLEAR PATH for Voters who may use a wheelchair to maneuver inside the Vote Center. *The diagram below is an example, spaces vary in sizes.*

1. Voter Information Centers (VICs)
2. Ranked-Choice Voting (RCV) Information Center
3. Facsimile Ballot Notice/Language Assistance Display Tables
4. Poll Pad Operator Table
5. Voter Information Guide (VIG) On Demand Printer Table
6. Ballot On Demand (BOD) Operator Table
7. Turquoise Official Ballots Bag Table
8. Official Ballots Delivery Cart
9. Supply Delivery Box
10. Accessible Voting Booths*
11. Standard Voting Booths
12. Touchscreen Voting Booths** ✓

*Minimum of one (1) Accessible Voting Booth
 **Minimum of four (4) Touchscreen Voting Booths




NOTE: BOD, VIG On Demand, and Ballot Marking Touchscreen equipment are only to be set up on mornings of Early Voting Days and Election Day.

TASK 7 SET UP OFFICIAL TABLES

1. **RETRIEVE** the 4-foot and 5-foot tables from the Supply Delivery Box:
 - 4-foot tables are used for displaying VIG On Demand and miscellaneous Election Worker supplies placed behind both Poll Pad and BOD Operator tables, away from the public.
 - 5-foot tables are used for the Poll Pad Operator table, BOD Operator table, and displaying State and County Voter Information Guides with the Facsimile Ballot Notice Tri-fold.

RECOMMENDED: For 11-day Vote Centers, set up another Poll Pad table starting on the Saturday before Election Day. For 4-day Vote Centers, set up another Poll Pad table from the first day of voting.


OFFICIAL TABLE DIAGRAM: FRIDAY SET UP



POLL PAD OPERATOR TABLE

1. Voter Fraud Telephone Cards
2. American Sign Language (ASL) Interpretation Available Sign
3. Pens
4. Touchscreen Stylus
5. Accessible Supplies (Magnifier, Pen with Grip, Signature Guides)
6. Help America Vote Act (HAVA) Requirements Binder
7. Language Color Guide Sign on stand
8. Language Hotline Sign on stand
9. Youth Voting VIG and Facsimile Ballot Sign on stand

NOTE: The diagram above is an example, spaces and set up may vary.

**BALLOT ON DEMAND OPERATOR TABLE**

- 10. Pens
- 11. Secrecy Sleeves

NOTE: The diagram above is an example, spaces and set up may vary.

TASK 8 LABEL COLORED BAGS


1. While at the Vote Center, **WRITE** the Vote Center Location number on one (1) of each of the labels of the colored bags.
 - Gray Voided/Surrendered Vote by Mail Ballots Bag
 - Purple Spoiled Ballots Bag
 - Teal Unscanned Voted Ballots Bag
 - Lime Bag




2. **SEAL** the Lime Bag's zipper with a White Security Seal.
3. **RETURN** to the Official Ballots Delivery Cart after labeling.

TASK 9 SET UP VOTING BOOTHS


SUPPLIES LOCATED IN THE SUPPLY DELIVERY BOX




1. **RETRIEVE** the blue plastic cases and **UNLATCH** the black tabs on each side.





2. **SEPARATE** the two (2) pieces to create two separate voting booths.




3. **UNHOOK** S-hook. **REMOVE** the Privacy Shield and legs from the inside of the booth.



4. **TURN** the booth upside down. **PUT** each leg halves together then **INSERT** each leg into the holes.



5. **STAND** the booth on legs.



6. **INSTALL** the Privacy Shield in the three (3) grooves in the base of the booth. **SECURE** Privacy Shield by pulling bungee cords through slits in Privacy Shield, from the outside in.


TASK 10 SET UP ACCESSIBLE VOTING BOOTH(S)




USE Booth marked with the Accessibility Symbol decal or White Velcro tab/masking tape on the handle.




Accessible Voting Booths have shorter legs than a standard Voting Booth and require a set of two (2) Adapters.
(Located in Opening Polls Supply Box.)




1. Before installing the legs, **INSTALL** Adapter in the front of the booth.



2. **LOCK IN** Adapter by pushing tab to the downward position.




3. **INSERT** the shorter legs into the holes of the Adapters and the holes of the booth.




4. **STAND** the booth up. **INSTALL** the Privacy Shield in the three (3) grooves in the base of the booth. **SECURE** Privacy Shield by pulling bungee cords through slits in Privacy Shield, from the outside in.

TASK 11 SET UP TOUCHSCREEN VOTING BOOTHS



SUPPLIES LOCATED IN THE SUPPLY DELIVERY BOX



1. **REMOVE** Velcro holding the booth together and **UNFOLD**.



2. **LIFT** table from back.



3. **LINE UP** latch from underneath the table and **SLIDE** latch to lock and secure.




4. **ATTACH** "Scroll Up/Down" Instructions sign to the front left vertical support using the attached velcro strip. The sign can be found in the Opening Polls Supply Box.


TASK 12 POST INSIDE SIGNS

NOTE: All signs must be visible and easily accessible to Voters and Observers.

SPANISH SAMPLE BALLOT



VOTER INFORMATION CENTER (VIC)



- **GRAB** any Voter Information Guide (VIG) and open to VIG Spanish Sample Ballot Page. **POST** by taping near the Poll Pad table, visible to Voters, after. (CEC § 14201)
- **PLACE** anywhere inside Vote Center (total of 4).

EARLY BALLOT PICK UP




TAMPERING WARNING



- **PLACE** near the inside entrance of the Vote Center.
- **PLACE** anywhere inside Vote Center.

NOTE: All signs must be visible and easily accessible to Voters and Observers.

FACSIMILE BALLOTS NOTICE TRI-FOLD, LANGUAGE ASSISTANCE & VOTER INFORMATION GUIDES



SCROLL UP/DOWN INSTRUCTIONS




- **PLACE** Tri-fold on a 5-foot table, beside the Poll Pad Operator Table.
- **TAPE** the Language Assistance sign on the edge of the table, facing out.
- **PLACE** State and County Voter Information Guides on top of the table.

- **ATTACH** sign to the front left vertical support of each Touchscreen Voting Booth using the attached velcro strip.

NOTE: Make sure there are 5 of the provided VIGs in each language displayed on the table at all times. Replenish the VIGs as necessary.

The Ballot Type is located on the lower left side of the VIG (e.g. 001, 002, etc.)



TASK 12 POST INSIDE SIGNS


NOTE: All signs must be visible and easily accessible to Voters and Observers.

ASL INTERPRETATION AVAILABLE



- **PLACE** signage about interpreting services at the entrance of the Vote Center and at the Poll Pad Operator Table.


VOTER FRAUD INFORMATION NOTICE



- **POST** anywhere inside Vote Center.

NOTE: All signs must be visible and easily accessible to Voters and Observers.

RANKED-CHOICE VOTING (RCV) INFORMATION CENTER



- **PLACE** RCV Information Center (2 total) anywhere inside the Vote Center.
- **PLACE** RCV Information pamphlets in the 6 plastic holders on a 4-foot table, beside the RCV Information Center. **REMOVE** any rubber bands holding the pamphlets together.

NOTE: Make sure there are RCV Information pamphlets in each language in the plastic holders at all times. Replenish the pamphlets as necessary.

- Each plastic holder has pockets for 6 languages.
- The RCV Information pamphlets and plastic holders can be found in the Official Ballots Delivery Cart

- **TAPE** the RCV Information Notice signs (found in the Opening Polls Supply Box) on the edge of the table, facing out.

OPENING

OPENING

VOTING MUST START AT SCHEDULED TIME

DO NOT DELAY SETTING UP THE VOTE CENTER. VOTING MUST START AT THE SCHEDULED START TIME!

NOTE: If Vote Center is locked, **CONTACT** the Election Worker Hotline at (510) 835-7205.

TASK 1 GIVE OUT BADGES

DAILY DAILY DAILY DAILY DAILY



- All Election Workers **MUST** wear their Election Worker Badges at all times, with their names clearly visible. Bilingual Election Workers **MUST** wear badges identifying the language they speak. Badges are located in the Opening Polls Supply Box.

TASK 2 CRADLEPOINT ROUTER SET UP

DAILY

DAILY

DAILY

DAILY


DAILY

SUPPLIES LOCATED IN THE OFFICIAL BALLOTS DELIVERY CART



1. The Cradlepoint Internet Routers are located within a protective case. **REMOVE** one set of contents from the Cradlepoint case and its protective foam packaging. **PLACE** it where it would have the best signal, also within a few feet of the Poll Pad. **PLACE** the foam and case aside.

NOTE: One (1) Cradlepoint set contains the router, two (2) flat antennas, and one (1) power cable.



2. **SCREW** the two (2) Cradlepoint antennas into the ports. **BEND** them (at the joints) so they are spread out for the best connectivity. **DO NOT SCREW** any into the center port.



3. **CONNECT** the power cord to the back of the Cradlepoint, **CONNECT** the power cord to a power source, and then **FLIP** the power switch, located beside the connection, upward to turn it on.

TASK 2 CRADLEPOINT ROUTER SET UP

DAILY

DAILY

DAILY


DAILY

DAILY

SUPPLIES LOCATED IN THE OFFICIAL BALLOTS DELIVERY CART

4. **Full connectivity may take up to 15 minutes after Cradlepoint is powered on.** The blue lights on the front determine the signal strength. Blue, orange, and green must be on for full connectivity.

If any of the lights are not on, UNPLUG AND PLUG back in to reconnect. **CALL** Election Worker Hotline to assess.



TASK 3 POLL PAD SET UP

DAILY


DAILY

DAILY



DAILY

DAILY


SUPPLIES LOCATED IN THE OFFICIAL BALLOTS DELIVERY CART




1. **RETRIEVE** one (1) green Poll Pad transport case from the Official Ballots Delivery Cart. **REMOVE** Ballot Form Printer, adapter, and power cord from the case.



2. **PLUG** the connector into the back of the printer. Then **PLUG** the printer power cord into a surge protector.



3. The ON/OFF switch is located on the left side of the printer. **SWITCH** to the "ON" position.



The green "POWER" light (*located on the front of the printer*) should be illuminated.

TASK 3 POLL PAD SET UP

DAILY


DAILY

DAILY

DAILY


DAILY

SUPPLIES LOCATED IN THE OFFICIAL BALLOTS DELIVERY CART




4. **ATTACH** the stand arm to the Poll Pad shell by pressing the buttons on the side of the arm, then **PLACE** in circular opening. **RELEASE** buttons and **ROTATE** the arm until it clicks.

5. **PLACE** stand arm into Poll Pad base.
Once attached, **ROTATE** Poll Pad to a landscape position.




6. **PLUG** the lightning connector into the Poll Pad, then **PLUG** the power adapter into a power source.



7. **PRESS** the power button on the top right edge of the unit until you see the Apple logo.



8. **PRESS** the application icon at the bottom of the screen.



9. **CHECK THE FOLLOWING:**
 - Screen says “Alameda County”
 - Election name and date
 - **IMPORTANT:** Verify the Vote Center location is correct
 - Battery life is close to full and/or being charged

TASK 3 POLL PAD SET UP

DAILY

DAILY

DAILY

DAILY

DAILY

SUPPLIES LOCATED IN THE OFFICIAL BALLOTS DELIVERY CART

10. POLL PAD WILL BE PASSWORD PROTECTED.

PRESS “GET STARTED” to proceed. **ENTER** the Poll Pad username and password (*located in the Cell Phone Pouch inside the Captain’s Supply Box*).



11. A green printer icon on the Poll Pad means you are connected to the printer. **PRESS** the green printer icon, then **PRESS** Print Test Receipt and a sample receipt will print.

12. The Poll Pad will automatically connect to the Cradlepoint Router’s WiFi network. **MAKE SURE** both the cloud icon is green and the Poll Pad is connected to the WiFi (as indicated, **marked orange**). **PRESS** the cloud icon to confirm that the synchronization is finished.



Poll Pad is paired with the printer. A receipt will print out for checked-in voter.



Poll Pad is currently connected and synchronizing with the central election database.



Poll Pad recognizes the printer and is currently in the process of pairing with the device.



Poll Pad is in the process of connecting to the Election database.



Poll Pad is not paired with the printer. **PROCEED** to “**NOT PRINTING / STOPS PRINTING**” Section (pg. 114).



Poll Pad is currently disconnected and not synchronizing with the Election database. Poll Pad will continue to work and check-in voters. **CONTACT** the Election Worker Hotline.

NOTE: Poll Pad label number and Printer label number must match in order to connect.

DAILY


DAILY

DAILY

DAILY

DAILY

2 PERSON RULE




California Elections Code Section 19240 requires that California voting system standards and elections comply with the provisions of the federal Help America Vote Act (HAVA) that require voting systems be accessible for individuals with disabilities.

California Secretary of State Guidelines require two (2) Election Workers perform the following procedures:

BOD PRINTER

1. With assistance from another Election Worker, carefully **PLACE** one of the BOD Printing Carts beside the BOD Officer table. **LOCK** the wheels in place by pressing on the brake on the bottom wheels.
2. **REMOVE** the White Security Seals from top and the front door of the cart, as seen below. **RETRIEVE** the BOD Printing Cart key located in the Captain Supply Box, within the Cell Phone Pouch.



3. **USE** the key to unlock the front door of the BOD Printing Cart. To keep the door propped open, carefully **SWING** the door all the way to the right until it touches the side of the cart. A built-in magnet will keep the door open.
4. Below the BOD Printer is a drawer containing the BOD Laptop and power cable for the BOD Printing Cart.

DAILY

DAILY

DAILY

DAILY

DAILY



5. **REMOVE** the power cable and **PLUG** it into the circular outlet located on the left side of the outer surface of the cart. **CONNECT** the opposite side of the cable into a power source/surge protector.



6. **TURN** the key counter-clockwise to unlock the laptop compartment lid, then **REMOVE** the key. **FLIP OPEN** lid.

NOTE: When connected to a power source, the BOD printer should turn on automatically. If it does not, manually turn it on by holding the white power button, located to the right of the LCD screen, until the BOD power is on



7. **FLIP UP** safety latch to the right of the laptop compartment. **SLIDE** the cart's top shelf to the left, revealing the Printer inside.



8. When the shelf is fully extended to the left, **PULL DOWN** the sliding shelf locks located underneath the sliding shelf.

NOTE: There are two locks: one on the front side and one on the back side.

DAILY

DAILY


DAILY

DAILY

DAILY



9. **RETRIEVE** the BOD Laptop box from the drawer.



10. **REMOVE** the BOD Laptop from the box and **PLACE** on the black laptop mat. **PLUG IN** the cables on top of the BOD Printing Cart into the available ports on the laptop. **RETURN** the laptop box to the drawer and **CLOSE** the drawer.



11. **REMOVE** the velcro strap from the rear side of the printer.



12. **VERIFY** the Ballot paper inside the BOD Printer is lying flat by removing Orange Security Seal from the bottom-front paper tray. Once the paper is confirmed to be lying flat within, **CLOSE & SECURE** the paper tray by placing a new Orange Security Seal, covering both the tray and part of the BOD Printer. **PLACE** the removed Orange Security Seal on the Seal Verification Form. All other seals on the Printer must remain on at all times.

DAILY

DAILY

DAILY

DAILY

DAILY

SUPPLIES LOCATED IN THE OFFICIAL BALLOTS DELIVERY CART

BOD LAPTOP




1. **POWER ON** Laptop, **SELECT** "MBPUser", then **SIGN IN** by entering password located on a card within the Captain (A) Cell Phone Pouch.


NOTE: Laptop must be connected to the charger at all times.



2. **OPEN** "EMS Mobile Ballot Production" application on the desktop by clicking the icon.




3. **CLICK** "File" on the top-left corner of the window, **CLICK** "Open Project", then **SELECT** the Election name, then **CLICK** "OK".



2. **CONNECT** Laptop Charger to VIG On Demand Laptop, into the hole with the power symbol (eg. ) beside it. **Make sure not to plug it into the headphone jack.**

NOTE: Laptop must be connected to the charger at all times.

3. **CONNECT** Laptop Charger and Printer power cable to the surge protector.



DAILY




DAILY

DAILY

DAILY

DAILY

SUPPLIES LOCATED IN THE OFFICIAL BALLOTS DELIVERY CART



NOTE: Laptop must be connected to the charger at all times.


DAILY

DAILY


DAILY

DAILY


DAILY



8. Make sure “user” profile is selected before signing in. **CLICK** “Sign in” button.



9. **DOUBLE CLICK** “Start Here” icon on the desktop to start the program.



10. If the screen shown above does not appear, **RESTART** the computer to try again.

OFFICIAL TABLE DIAGRAM

DAILY



DAILY

DAILY

DAILY

DAILY

NOTE: All electronic equipment (Poll Pads, BOD Printer, VIG On Demand Printer, and Laptops) must be set up every morning before opening, starting the opening Saturday. *The diagram below is an example, spaces and set up may vary.*




POLL PAD OPERATOR TABLE


1. Voter Fraud Telephone Cards
2. Replacement Vote by Mail Envelopes
3. American Sign Language (ASL) Interpretation Available Sign
4. Pens
5. Touchscreen Stylus
6. Accessible Supplies (Magnifier sheet, Pen with Grip, Signature Guides, and Magnifying Glass)
7. Help America Vote Act (HAVA) Requirements Binder
8. Language Color Guide Sign on stand
9. Electronic Poll Pad
10. Language Hotline Sign on stand
11. Conditional Provisional Registration Forms (unused)
12. Poll Pad Ballot Form Printer
13. Youth Voting VIG and Facsimile Ballot Sign on stand
14. Gray Voided/Surrendered Vote by Mail Ballots Bag

NOTE: Registration Forms must be within close proximity of the Poll Pad operator table.

NOTE: All electronic equipment (Poll Pads, BOD Printer, VIG On Demand Printer, and Laptops) must be set up every morning before opening, starting the opening Saturday. *The diagram below is an example, spaces and set up may vary.*



- BALLOT ON DEMAND OPERATOR TABLE**
- 15. Pens
 - 16. Secrecy Sleeves
 - 17. BOD Audit Binder
 - 18. Purple Spoiled Ballots Bag*
 - 19. Teal Unscanned Voted Ballots Bag (for Voted Vote Center Ballots)*
- * Place underneath table*



- VOTER INFORMATION GUIDE ON DEMAND TABLE**
- 20. VIG On Demand Solid State Drive
 - 21. VIG On Demand Laptop
 - 22. Mouse
 - 23. VIG On Demand Printer

TASK 6 SET UP TURQUOISE OFFICIAL BALLOTS BAG

DAILY

DAILY

DAILY

DAILY

DAILY

SUPPLIES LOCATED IN THE OFFICIAL BALLOTS DELIVERY CART



1. **RETRIEVE** a Turquoise Official Ballots Bag, a bin, a cable, and padlock with key. **PLACE** these items on a 4-foot table.
2. **OPEN** the top flap of the bag.



3. **LIFT** the bag upright.
4. **SECURE** the metal frame to the Velcro strips on each side inside the bag.



5. **PLACE** the bin next to the bag.



6. **THREAD** the cable through the loop at the bottom back of the bag, and through the legs of the table.
7. **SECURE** the cable with the padlock and key. **STORE** the key in the Captain Box for use.
8. The Turquoise Official Ballots Bag and bin are now ready for inspection by the first voter

DAILY

DAILY

DAILY

DAILY

DAILY

2 PERSON RULE



California Elections Code Section 19240 requires that California voting system standards and elections comply with the provisions of the federal Help America Vote Act (HAVA) that require voting systems be accessible for individuals with disabilities.

California Secretary of State Guidelines require two (2) Election Workers perform the following procedures:

** Refer to Ballot Marking Touchscreen Setup Section, starting on pg. 75*



BALLOT MARKING TOUCHSCREEN



PRINTER



ATI (Audio Tactile Interface)



POLL WORKER CARD*

** Located with the Cell Phone Pouch*

PAGE 1

SEAL VERIFICATION FORM

LOCATION
1234 MAIN STREET
CITY

VC000001
ELECTION NAME - MM/DD/YYYY



RED SECURITY SEAL2 PERSON RULE

1. VERIFY that the Red Security Seal serial number matches the Ballot Marking Touchscreens and this form.

If the serial numbers **DO NOT** match or if the seal is compromised or tampered, **CALL** the Registrar of Voters Election Worker Hotline immediately.

2. FOLLOW Touchscreen Powering On/Off instructions.

If Ballot Marking Touchscreen does not power on automatically, **FOLLOW** instructions in Election Worker Guide.

As necessary, **RESEAL** the Ballot Marking Touchscreen, then **RECORD** the replacement Red Security Seal number.

3. Election Workers **MUST COMPLETE** the "Verified By" section.

ASSET ID
A000001

DAY #	RED SEAL #	REPLACEMENT #	REPLACEMENT #
1	(051804)		
2			
3			
ELECTION DAY			

VERIFIED BY	
PRINTED NAME	SIGNATURE
WORKER 1	
WORKER 2	
WORKER 1	
WORKER 2	
WORKER 1	
WORKER 2	
WORKER 1	
WORKER 2	

OPENING - BLUE SECURITY SEAL2 PERSON RULE

1. VERIFY that the Blue Security Seal is intact.

If the security seal is compromised or tampered, **CALL** the Registrar of Voters Election Worker Hotline immediately.

2. Election Workers **MUST COMPLETE** the "Verified By" section.

DAY #	VERIFIED BY
	INITIALS
1	WORKER 1
	WORKER 2
2	WORKER 1
	WORKER 2
3	WORKER 1
	WORKER 2
ELECTION DAY	WORKER 1
	WORKER 2

AReplacement Red Security Seal numbers

BElection Workers' printed name & initials verifying Red Security Seals

CElection Workers' initials verifying Blue Security Seals

PAGE 2

RED SECURITY SEAL2 PERSON RULE

1. The Red Security Seal must remain intact throughout the day.

If the seal is compromised or tampered, **CALL** the Registrar of Voters Election Worker Hotline immediately.

2. VERIFY the Red Security Seal at the specified times, then **INITIAL** the boxes below.

3. Election Workers **MUST COMPLETE** the "Verified By" section.

DAY #	VERIFIED BY
	INITIALS
1	WORKER 1
	WORKER 2
2	WORKER 1
	WORKER 2
3	WORKER 1
	WORKER 2
ELECTION DAY	WORKER 1
	WORKER 2

DAY #	VERIFIED BY
	INITIALS
1	WORKER 1
	WORKER 2
2	WORKER 1
	WORKER 2
3	WORKER 1
	WORKER 2
ELECTION DAY	WORKER 1
	WORKER 2

DAY #	VERIFIED BY
	INITIALS
1	WORKER 1
	WORKER 2
2	WORKER 1
	WORKER 2
3	WORKER 1
	WORKER 2
ELECTION DAY	WORKER 1
	WORKER 2

DAY #	VERIFIED BY
	INITIALS
1	WORKER 1
	WORKER 2
2	WORKER 1
	WORKER 2
3	WORKER 1
	WORKER 2
ELECTION DAY	WORKER 1
	WORKER 2

DAY #	VERIFIED BY
	INITIALS
1	WORKER 1
	WORKER 2
2	WORKER 1
	WORKER 2
3	WORKER 1
	WORKER 2
ELECTION DAY	WORKER 1
	WORKER 2

DAY #	VERIFIED BY
	INITIALS
1	WORKER 1
	WORKER 2
2	WORKER 1
	WORKER 2
3	WORKER 1
	WORKER 2
ELECTION DAY	WORKER 1
	WORKER 2

D

E

F

Election Workers' initials verifying Red Security Seals periodically

Any removed Orange Security Seals

Any removed Red Security Seals during Election

NOTE: Place any white Security Seals removed in the Security Seal Envelope.

PAGE 3

ORANGE SEALS REMOVED FROM PRINTERS

1. PLACE any removed Orange Security Seals on this page of the Seal Verification Form.

2. REPLACE the removed Orange Security Seal with a new one.

PAGE 4

RED SECURITY SEALS REMOVED FROM BALLOT MARKING TOUCHSCREENS

1. PLACE any removed Red Security Seals on this page of the Seal Verification Form.

2. FOLLOW instructions on the Red Security Seal Verification Form.

ELECTION WORKER GUIDE

65

PAGE 1

SEAL VERIFICATION FORM

LOCATION: 1234 MAIN STREET, CITY

V0000001
ELECTION NAME - BRADDOYVY

RED SECURITY SEAL 2 PERSON RULE

1. **VERIFY** that the Red Security Seal serial number matches the Ballot Marking Touchscreen and this form.

- If the serial numbers **DO NOT** match or if the seal is compromised or tampered, **CALL** the Registrar of Voters Election Worker Hotline immediately.

2. **FOLLOW** Touchscreen Powering On/Off instructions.

- If Ballot Marking Touchscreen does not power on automatically, **FOLLOW** instructions in Election Worker Guide.
- As necessary, **RESEAL** the Ballot Marking Touchscreen. **RECORD** the replacement Red Security Seal number.

3. Election Workers **MUST COMPLETE** the "Verified By" section.

ASSET ID: A000001

DAY #	RED SEAL #	REPLACEMENT	REPLACEMENT	PRINTED NAME	VERIFIED BY	INITIALS
1	001004			WORKER 1		
				WORKER 2		
2				WORKER 1		
				WORKER 2		
3				WORKER 1		
				WORKER 2		
4				WORKER 1		
				WORKER 2		
5				WORKER 1		
				WORKER 2		
6				WORKER 1		
				WORKER 2		
7				WORKER 1		
				WORKER 2		
8				WORKER 1		
				WORKER 2		
9				WORKER 1		
				WORKER 2		

A **B**

- A** Replacement Red Security Seal numbers
- B** Election Workers' printed name & initials verifying Red Security Seals
- C** Election Workers' initials verifying Red Security Seals periodically

PAGE 2

RED SECURITY SEAL 2 PERSON RULE

1. The **Red Security Seal** must remain intact throughout the day.

- If the seal is compromised or tampered, **CALL** the Registrar of Voters Election Worker Hotline immediately.

2. **VERIFY** the Red Security Seal at the specified times, then **INITIAL** the boxes below.

3. Election Workers **MUST COMPLETE** the "Verified By" section.

10:00 AM			1:00 PM			4:30 PM		
DAY #	VERIFIED BY	INITIALS	DAY #	VERIFIED BY	INITIALS	DAY #	VERIFIED BY	INITIALS
1	WORKER 1		1	WORKER 1		1	WORKER 1	
	WORKER 2			WORKER 2			WORKER 2	
2	WORKER 1		2	WORKER 1		2	WORKER 1	
	WORKER 2			WORKER 2			WORKER 2	
3	WORKER 1		3	WORKER 1		3	WORKER 1	
	WORKER 2			WORKER 2			WORKER 2	
4	WORKER 1		4	WORKER 1		4	WORKER 1	
	WORKER 2			WORKER 2			WORKER 2	
5	WORKER 1		5	WORKER 1		5	WORKER 1	
	WORKER 2			WORKER 2			WORKER 2	
6	WORKER 1		6	WORKER 1		6	WORKER 1	
	WORKER 2			WORKER 2			WORKER 2	
7	WORKER 1		7	WORKER 1		7	WORKER 1	
	WORKER 2			WORKER 2			WORKER 2	
8	WORKER 1		8	WORKER 1		8	WORKER 1	
	WORKER 2			WORKER 2			WORKER 2	
9	WORKER 1		9	WORKER 1		9	WORKER 1	
	WORKER 2			WORKER 2			WORKER 2	
10	WORKER 1		10	WORKER 1		10	WORKER 1	
	WORKER 2			WORKER 2			WORKER 2	

C

12:30 PM		5:30 PM		7:30 PM	
WORKER 1	WORKER 2	WORKER 1	WORKER 2	WORKER 1	WORKER 2

- D** Election Workers' initials verifying Blue Security Seals
- E** Any removed Orange Security Seals
- F** Any removed Red Security Seals during Election

NOTE: Place any white Security Seals removed in the Security Seal Envelope.

PAGE 3

SEAL VERIFICATION FORM

LOCATION: 1234 MAIN STREET, CITY

123456
General Election - 11/03/2020

OPENING BLUE SECURITY SEAL 2 PERSON RULE

1. **VERIFY** the Blue Security Seal is intact.

2. Poll Workers **MUST COMPLETE** the "Verified By" section.

If the seal is compromised or tampered, call the Registrar of Voters immediately at (510) 835-0320.

DAY	VERIFIED BY	INITIALS
DAY 1	WORKER 1	
	WORKER 2	
DAY 2	WORKER 1	
	WORKER 2	
DAY 3	WORKER 1	
	WORKER 2	
DAY 4	WORKER 1	
	WORKER 2	
DAY 5	WORKER 1	
	WORKER 2	
DAY 6	WORKER 1	
	WORKER 2	
DAY 7	WORKER 1	
	WORKER 2	
DAY 8	WORKER 1	
	WORKER 2	
DAY 9	WORKER 1	
	WORKER 2	
DAY 10	WORKER 1	
	WORKER 2	
DAY 11	WORKER 1	
	WORKER 2	

D

PAGE 5

ORANGE SEALS REMOVED FROM PRINTERS

1. **PLACE** any removed Orange Security Seals on this page of the Seal Verification Form.

2. **REPLACE** the removed Orange Security Seal with a new one.

E

PAGE 6

RED SECURITY SEALS REMOVED FROM BALLOT MARKING TOUCHSCREENS

1. **PLACE** any removed Red Security Seals on this page of the Seal Verification Form.

2. **FOLLOW** instructions on the Red Security Seal Verification Form.

F

DAILY

DAILY

DAILY

DAILY

DAILY

SEAL VERIFICATION FORM

LOCATION: 1234 MAIN STREET
CITY: ALABAMA COUNTY
ELECTION NAME: MMDDYYYY

RED SECURITY SEAL

1. **VERIFY** that the Red Security Seal serial number matches the Ballot Marking Touchscreen and this form.

- If the serial numbers **DO NOT** match or if the seal is compromised or tampered, **CALL** the Registrar of Voters Election Worker Hotline immediately.

2. **FOLLOW** Touchscreen Powering On/Off instructions.

3. If Ballot Marking Touchscreen does not power on automatically, **FOLLOW** instructions in Election Worker Guide.

4. In instances of **RECALL** for Ballot Marking Touchscreen, then **RECORD** the replacement Red Security Seal number.

5. Election Workers **MUST COMPLETE** the "Verified By" section.


DAY #	RED SEAL #	REPLACEMENT#	REPLACEMENT#	PRINTED NAME	SIGNATURE
1	(051804)			WORKER 1	
2				WORKER 2	
3				WORKER 1	
4				WORKER 2	
5				WORKER 1	
6				WORKER 2	
7				WORKER 1	
8				WORKER 2	
9				WORKER 1	
10				WORKER 2	
ELECTION DAY				WORKER 1	
				WORKER 2	

ASSET ID: A000001

1. **LOCATE** the Seal Verification Forms inside the Captain Supply Box.

NOTE: Each Ballot Marking Touchscreen has its own Seal Verification Form.

2. **ENSURE** the asset number on each Ballot Marking Touchscreen matches each corresponding Seal Verification Form. The asset number is found on the back side of the Ballot Marking Touchscreen base.



SEAL VERIFICATION FORM

LOCATION: 1234 MAIN STREET
CITY: ALABAMA COUNTY
ELECTION NAME: MMDDYYYY

RED SECURITY SEAL

1. **VERIFY** that the Red Security Seal serial number matches the Ballot Marking Touchscreen and this form.

- If the serial numbers **DO NOT** match or if the seal is compromised or tampered, **CALL** the Registrar of Voters Election Worker Hotline immediately.

2. **FOLLOW** Touchscreen Powering On/Off instructions.

3. If Ballot Marking Touchscreen does not power on automatically, **FOLLOW** instructions in Election Worker Guide.

4. In instances of **RECALL** for Ballot Marking Touchscreen, then **RECORD** the replacement Red Security Seal number.

5. Election Workers **MUST COMPLETE** the "Verified By" section.

DAY #	RED SEAL #	REPLACEMENT#	REPLACEMENT#	PRINTED NAME	SIGNATURE
1	(051804)			WORKER 1	
2				WORKER 2	
3				WORKER 1	
4				WORKER 2	
5				WORKER 1	
6				WORKER 2	
7				WORKER 1	
8				WORKER 2	
9				WORKER 1	
10				WORKER 2	
ELECTION DAY				WORKER 1	
				WORKER 2	

ASSET ID: A000001

OPENING - BLUE SECURITY SEAL

1. **VERIFY** that the Blue Security Seal is intact.

- If the security seal is compromised or tampered, **CALL** the Registrar of Voters Election Worker Hotline immediately.

2. Election Workers **MUST COMPLETE** the "Verified By" section.

DAY #	VERIFIED BY
1	WORKER 1
2	WORKER 2
3	WORKER 1
4	WORKER 2
5	WORKER 1
6	WORKER 2
7	WORKER 1
8	WORKER 2
9	WORKER 1
10	WORKER 2
ELECTION DAY	WORKER 1
	WORKER 2

3. **VERIFY** Blue Security Seal is intact. **Two (2) Election Workers must INITIAL** their names daily.

NOTE: Never remove any Blue Security Seal.

TASK 8 SEAL VERIFICATION FORM


DAILY

DAILY

DAILY

DAILY

DAILY



- While holding the base, **ROTATE** the Ballot Marking Touchscreen upwards.
- VERIFY** Red Security Seal serial number matches with Seal Verification Form. Two (2) Election Workers must **PRINT** their names and signatures daily.

SEAL VERIFICATION FORM																																																	
LOCATION 1234 MAIN STREET CITY		VC000001		ELECTION NAME - MMCCYYYYY																																													
RED SECURITY SEAL				2 PERSON RULE																																													
- If the serial numbers DON'T match or if the seal is compromised or tampered, CALL the Registrar of Voters Election Worker Hotline immediately. FOLLOW Touchscreen Prompting On/Off instructions. - If Ballot Marking Touchscreen does not power on automatically, FOLLOW instructions in Election Worker Guide. - As workers RESET the Ballot Marking Touchscreen, then RECORD the replacement Red Security Seal number.				ASSET ID AD00001																																													
2. Election Workers MUST COMPLETE the "Verified By" section.				<table border="1"> <thead> <tr> <th>DAY #</th> <th>RED SEAL #</th> <th>REPLACEMENT #</th> <th>REPLACEMENT #</th> <th>WORKER 1</th> <th>WORKER 2</th> <th>PRINTED NAME</th> <th>SIGNATURE</th> </tr> </thead> <tbody> <tr> <td>1</td> <td>(001004)</td> <td></td> <td></td> <td>WORKER 1</td> <td>WORKER 2</td> <td></td> <td></td> </tr> <tr> <td>2</td> <td></td> <td></td> <td></td> <td>WORKER 1</td> <td>WORKER 2</td> <td></td> <td></td> </tr> <tr> <td>3</td> <td></td> <td></td> <td></td> <td>WORKER 1</td> <td>WORKER 2</td> <td></td> <td></td> </tr> <tr> <td>ELECTION DAY</td> <td></td> <td></td> <td></td> <td>WORKER 1</td> <td>WORKER 2</td> <td></td> <td></td> </tr> </tbody> </table>						DAY #	RED SEAL #	REPLACEMENT #	REPLACEMENT #	WORKER 1	WORKER 2	PRINTED NAME	SIGNATURE	1	(001004)			WORKER 1	WORKER 2			2				WORKER 1	WORKER 2			3				WORKER 1	WORKER 2			ELECTION DAY				WORKER 1	WORKER 2		
DAY #	RED SEAL #	REPLACEMENT #	REPLACEMENT #	WORKER 1	WORKER 2	PRINTED NAME	SIGNATURE																																										
1	(001004)			WORKER 1	WORKER 2																																												
2				WORKER 1	WORKER 2																																												
3				WORKER 1	WORKER 2																																												
ELECTION DAY				WORKER 1	WORKER 2																																												
OPENING - BLUE SECURITY SEAL				2 PERSON RULE																																													
VERIFY that the Blue Security Seal is intact. - If the security seal is compromised or tampered, CALL the Registrar of Voters Election Worker Hotline immediately.				2. Election Workers MUST COMPLETE the "Verified By" section.																																													
<table border="1"> <thead> <tr> <th>DAY #</th> <th>WORKER 1</th> <th>WORKER 2</th> <th>PRINTED NAME</th> <th>SIGNATURE</th> </tr> </thead> <tbody> <tr> <td>1</td> <td>WORKER 1</td> <td>WORKER 2</td> <td></td> <td></td> </tr> <tr> <td>2</td> <td>WORKER 1</td> <td>WORKER 2</td> <td></td> <td></td> </tr> <tr> <td>3</td> <td>WORKER 1</td> <td>WORKER 2</td> <td></td> <td></td> </tr> <tr> <td>ELECTION DAY</td> <td>WORKER 1</td> <td>WORKER 2</td> <td></td> <td></td> </tr> </tbody> </table>				DAY #	WORKER 1	WORKER 2	PRINTED NAME	SIGNATURE	1	WORKER 1	WORKER 2			2	WORKER 1	WORKER 2			3	WORKER 1	WORKER 2			ELECTION DAY	WORKER 1	WORKER 2																							
DAY #	WORKER 1	WORKER 2	PRINTED NAME	SIGNATURE																																													
1	WORKER 1	WORKER 2																																															
2	WORKER 1	WORKER 2																																															
3	WORKER 1	WORKER 2																																															
ELECTION DAY	WORKER 1	WORKER 2																																															

NOTE: Rotating the Touchscreen upwards may cause it to tip over.

RED SECURITY SEAL					2 PERSON RULE																																																																																																																																																												
- The Red Security Seal must remain intact throughout the day. - If the seal is compromised or tampered, CALL the Registrar of Voters Election Worker Hotline immediately.																																																																																																																																																																	
2. VERIFY the Red Security Seal at the specified times, then INITIAL the boxes below.																																																																																																																																																																	
3. Election Workers MUST COMPLETE the "Verified By" section.																																																																																																																																																																	
10:00 AM <table border="1"> <thead> <tr> <th>DAY #</th> <th>WORKER 1</th> <th>WORKER 2</th> <th>PRINTED NAME</th> <th>SIGNATURE</th> </tr> </thead> <tbody> <tr> <td>1</td> <td>WORKER 1</td> <td>WORKER 2</td> <td></td> <td></td> </tr> <tr> <td>2</td> <td>WORKER 1</td> <td>WORKER 2</td> <td></td> <td></td> </tr> <tr> <td>3</td> <td>WORKER 1</td> <td>WORKER 2</td> <td></td> <td></td> </tr> <tr> <td>ELECTION DAY</td> <td>WORKER 1</td> <td>WORKER 2</td> <td></td> <td></td> </tr> </tbody> </table>		DAY #	WORKER 1	WORKER 2	PRINTED NAME	SIGNATURE	1	WORKER 1	WORKER 2			2	WORKER 1	WORKER 2			3	WORKER 1	WORKER 2			ELECTION DAY	WORKER 1	WORKER 2			1:00 PM <table border="1"> <thead> <tr> <th>DAY #</th> <th>WORKER 1</th> <th>WORKER 2</th> <th>PRINTED NAME</th> <th>SIGNATURE</th> </tr> </thead> <tbody> <tr> <td>1</td> <td>WORKER 1</td> <td>WORKER 2</td> <td></td> <td></td> </tr> <tr> <td>2</td> <td>WORKER 1</td> <td>WORKER 2</td> <td></td> <td></td> </tr> <tr> <td>3</td> <td>WORKER 1</td> <td>WORKER 2</td> <td></td> <td></td> </tr> <tr> <td>ELECTION DAY</td> <td>WORKER 1</td> <td>WORKER 2</td> <td></td> <td></td> </tr> </tbody> </table>		DAY #	WORKER 1	WORKER 2	PRINTED NAME	SIGNATURE	1	WORKER 1	WORKER 2			2	WORKER 1	WORKER 2			3	WORKER 1	WORKER 2			ELECTION DAY	WORKER 1	WORKER 2			4:30 PM <table border="1"> <thead> <tr> <th>DAY #</th> <th>WORKER 1</th> <th>WORKER 2</th> <th>PRINTED NAME</th> <th>SIGNATURE</th> </tr> </thead> <tbody> <tr> <td>1</td> <td>WORKER 1</td> <td>WORKER 2</td> <td></td> <td></td> </tr> <tr> <td>2</td> <td>WORKER 1</td> <td>WORKER 2</td> <td></td> <td></td> </tr> <tr> <td>3</td> <td>WORKER 1</td> <td>WORKER 2</td> <td></td> <td></td> </tr> <tr> <td>ELECTION DAY</td> <td>WORKER 1</td> <td>WORKER 2</td> <td></td> <td></td> </tr> </tbody> </table>		DAY #	WORKER 1	WORKER 2	PRINTED NAME	SIGNATURE	1	WORKER 1	WORKER 2			2	WORKER 1	WORKER 2			3	WORKER 1	WORKER 2			ELECTION DAY	WORKER 1	WORKER 2			12:30 PM <table border="1"> <thead> <tr> <th>DAY #</th> <th>WORKER 1</th> <th>WORKER 2</th> <th>PRINTED NAME</th> <th>SIGNATURE</th> </tr> </thead> <tbody> <tr> <td>1</td> <td>WORKER 1</td> <td>WORKER 2</td> <td></td> <td></td> </tr> <tr> <td>2</td> <td>WORKER 1</td> <td>WORKER 2</td> <td></td> <td></td> </tr> <tr> <td>3</td> <td>WORKER 1</td> <td>WORKER 2</td> <td></td> <td></td> </tr> <tr> <td>ELECTION DAY</td> <td>WORKER 1</td> <td>WORKER 2</td> <td></td> <td></td> </tr> </tbody> </table>		DAY #	WORKER 1	WORKER 2	PRINTED NAME	SIGNATURE	1	WORKER 1	WORKER 2			2	WORKER 1	WORKER 2			3	WORKER 1	WORKER 2			ELECTION DAY	WORKER 1	WORKER 2			5:30 PM <table border="1"> <thead> <tr> <th>DAY #</th> <th>WORKER 1</th> <th>WORKER 2</th> <th>PRINTED NAME</th> <th>SIGNATURE</th> </tr> </thead> <tbody> <tr> <td>1</td> <td>WORKER 1</td> <td>WORKER 2</td> <td></td> <td></td> </tr> <tr> <td>2</td> <td>WORKER 1</td> <td>WORKER 2</td> <td></td> <td></td> </tr> <tr> <td>3</td> <td>WORKER 1</td> <td>WORKER 2</td> <td></td> <td></td> </tr> <tr> <td>ELECTION DAY</td> <td>WORKER 1</td> <td>WORKER 2</td> <td></td> <td></td> </tr> </tbody> </table>		DAY #	WORKER 1	WORKER 2	PRINTED NAME	SIGNATURE	1	WORKER 1	WORKER 2			2	WORKER 1	WORKER 2			3	WORKER 1	WORKER 2			ELECTION DAY	WORKER 1	WORKER 2			7:30 PM <table border="1"> <thead> <tr> <th>DAY #</th> <th>WORKER 1</th> <th>WORKER 2</th> <th>PRINTED NAME</th> <th>SIGNATURE</th> </tr> </thead> <tbody> <tr> <td>1</td> <td>WORKER 1</td> <td>WORKER 2</td> <td></td> <td></td> </tr> <tr> <td>2</td> <td>WORKER 1</td> <td>WORKER 2</td> <td></td> <td></td> </tr> <tr> <td>3</td> <td>WORKER 1</td> <td>WORKER 2</td> <td></td> <td></td> </tr> <tr> <td>ELECTION DAY</td> <td>WORKER 1</td> <td>WORKER 2</td> <td></td> <td></td> </tr> </tbody> </table>		DAY #	WORKER 1	WORKER 2	PRINTED NAME	SIGNATURE	1	WORKER 1	WORKER 2			2	WORKER 1	WORKER 2			3	WORKER 1	WORKER 2			ELECTION DAY	WORKER 1	WORKER 2		
DAY #	WORKER 1	WORKER 2	PRINTED NAME	SIGNATURE																																																																																																																																																													
1	WORKER 1	WORKER 2																																																																																																																																																															
2	WORKER 1	WORKER 2																																																																																																																																																															
3	WORKER 1	WORKER 2																																																																																																																																																															
ELECTION DAY	WORKER 1	WORKER 2																																																																																																																																																															
DAY #	WORKER 1	WORKER 2	PRINTED NAME	SIGNATURE																																																																																																																																																													
1	WORKER 1	WORKER 2																																																																																																																																																															
2	WORKER 1	WORKER 2																																																																																																																																																															
3	WORKER 1	WORKER 2																																																																																																																																																															
ELECTION DAY	WORKER 1	WORKER 2																																																																																																																																																															
DAY #	WORKER 1	WORKER 2	PRINTED NAME	SIGNATURE																																																																																																																																																													
1	WORKER 1	WORKER 2																																																																																																																																																															
2	WORKER 1	WORKER 2																																																																																																																																																															
3	WORKER 1	WORKER 2																																																																																																																																																															
ELECTION DAY	WORKER 1	WORKER 2																																																																																																																																																															
DAY #	WORKER 1	WORKER 2	PRINTED NAME	SIGNATURE																																																																																																																																																													
1	WORKER 1	WORKER 2																																																																																																																																																															
2	WORKER 1	WORKER 2																																																																																																																																																															
3	WORKER 1	WORKER 2																																																																																																																																																															
ELECTION DAY	WORKER 1	WORKER 2																																																																																																																																																															
DAY #	WORKER 1	WORKER 2	PRINTED NAME	SIGNATURE																																																																																																																																																													
1	WORKER 1	WORKER 2																																																																																																																																																															
2	WORKER 1	WORKER 2																																																																																																																																																															
3	WORKER 1	WORKER 2																																																																																																																																																															
ELECTION DAY	WORKER 1	WORKER 2																																																																																																																																																															
DAY #	WORKER 1	WORKER 2	PRINTED NAME	SIGNATURE																																																																																																																																																													
1	WORKER 1	WORKER 2																																																																																																																																																															
2	WORKER 1	WORKER 2																																																																																																																																																															
3	WORKER 1	WORKER 2																																																																																																																																																															
ELECTION DAY	WORKER 1	WORKER 2																																																																																																																																																															

- VERIFY & INITIAL** for the Red Security Seals at the three designated times indicated on the form.

NOTE: Security Seals must remain intact throughout the day. **If any Seal Verification Forms are missing, CONTACT** the Election Worker Hotline immediately.

TASK 9 POST OUTSIDE SIGNS

DAILY

DAILY

DAILY

DAILY

DAILY



FEATHER SIGNS

- PLACE** a set beside the entrance of the Vote Center.

CURBSIDE A-FRAME



- **PLACE** outside Vote Center, near the curb, preferably by an accessible parking spot.
- **ENSURE** the Curbside A-Frame is placed far enough back so that a parked vehicle will not block it.

DIRECTIONAL & ACCESSIBLE ENTRANCE A-FRAME



- **PLACE** outside Vote Center, pointing in the direction of the Vote Center.
- **PLACE** Accessible Entrance A-Frame outside Vote Center pointing towards the accessible entrance of the Vote Center.
- The Accessible Entrance A-Frame should be placed in a location that helps Voters locate an accessible path of travel, including a ramp.

ELECTIONEERING & CORRUPTION A-FRAMES



- **PLACE** a set beside the entrance of the Vote Center and another set at the area of Curbside Voting.


NOTE: Ensure no A-frame sign impedes the Voters' path of travel.

VOTE HERE TODAY!



- **POST** along the path of travel to the Vote Center, pointing in the direction of the Vote Center.

VOTE CENTER 100-FEET



- **POST** 100 feet (or 40 steps) in each direction from the main entrance of the Vote Center and the area of Curbside Voting.

ACCESSIBLE ENTRANCE



- **POST** along the accessible path of travel to the Vote Center, pointing in the direction of the Vote Center.

NOTE: All small directional signs must be visible, within eye-level for persons in wheelchairs, and easily accessible to Voters and Observers.

TASK 9 POST OUTSIDE SIGNS

DAILY

DAILY

DAILY

DAILY

DAILY


- **POST** these following posters next to the entrance of the Vote Center:

TOP TWO/ ELECTIONS IN CA



- Two (2) posters

VOTER BILL OF RIGHTS



- Two (2) posters



VOTE CENTER STREET INDEX




VOTE CENTER HOURS



NOTE: Poll Pad must be set up and connected to the Cradlepoint Router before proceeding.



1. Using one of the Poll Pads, **NAVIGATE** to the MAIN MENU, then **PRESS** "Pollworkers".
2. **ENTER** Election Worker's name by selecting "ADD POLL WORKER" located on the left of the screen.



3. Once the Election Worker's information is entered, **READ** the Oath presented above the signature line and **SIGN** name. **PRESS** "SIGN IN" when finished. Each Election Worker must repeat this process.

Before starting each day, SIGN IN by selecting the name, signing on the line below, then pressing "SIGN IN" to enter.

TASK 11 CHECK THE FOLLOWING

DAILY


DAILY

DAILY

DAILY


DAILY

OFFICIAL TABLE SET UP



- All tables are set up and ready for Voters
- **Gray Voided/Surrendered Vote by Mail Ballots, Purple Spoiled Ballots, Teal Unscanned Voted Ballots Bags** are placed under their respective tables
- Poll Pad and Cradlepoint are powered on and connected

SIGNS ARE POSTED




- **Inside** and **Outside** Signs are posted and visible to Voters and Observers
- Language Assistance Signs are posted.
- **A-Frames** are up and in their appropriate locations

ELECTION OFFICIAL BADGES




- Election Workers are wearing **badges at all times.**

BALLOT TROLLEYS & BAG ARE EMPTY



- **Yellow** Vote By Mail Ballots Trolley
- **Turquoise** Official Ballots Bag
- **Blue** Provisional Ballots Trolley
- **Lime Bag** (zipper must be sealed with White Security Seal)

VOTING BOOTHS ARE SET UP



- **Standard** Voting Booths
- **Accessible** Voting Booths
- **Touchscreen** Voting Booths

ASSIST OTHER ELECTION WORKERS WITH TASKS, IF FINISHED EARLY.

TASK 12 ANNOUNCE OPENING OF THE POLLS

DAILY

DAILY

DAILY

DAILY

DAILY

At the scheduled open time, **STEP OUTSIDE & MAKE THE ANNOUNCEMENT:**

“THE VOTE CENTER IS NOW OPEN!”

BALLOT MARKING TOUCHSCREEN SETUP

BALLOT MARKING TOUCHSCREEN SETUP

SETTING UP TOUCHSCREEN

TWO (2) PERSON RULE

DAILY

DAILY


DAILY

DAILY

DAILY


SUPPLIES LOCATED IN THE OFFICIAL BALLOTS DELIVERY CART

2 PERSON RULE




California Elections Code Section 19240 requires that California voting system standards and elections comply with the provisions of the federal Help America Vote Act (HAVA) that require voting systems be accessible for individuals with disabilities.


California Secretary of State Guidelines require two (2) Election Workers perform the following procedures:



1. **PLACE** the Ballot Marking Touchscreen case on a flat surface with the rolling handle on the bottom. **OPEN** the case.



2. **REMOVE** the small box containing the power cord from the case.



3. **REMOVE** the Ballot Marking Touchscreen and Audio Tactile Interface (ATI) with headphones attached out of the case using the handle behind the screen. While holding the Ballot Marking Touchscreen, **REMOVE** the protective packaging.
4. **PLACE** the Ballot Marking Touchscreen in Touchscreen Voting Booth.
5. **PLACE** the packaging back in the case, then **ZIP CLOSE**. **RETURN** the Ballot Marking Touchscreen Case to the Official Ballots Delivery Cart.

PRINTER SETUP

TWO (2) PERSON RULE

DAILY


DAILY

DAILY


DAILY

DAILY


SUPPLIES LOCATED IN THE OFFICIAL BALLOTS DELIVERY CART




1. **PLACE** the Printer case on a flat surface with the rolling handle on the bottom. **OPEN** the case.




2. **REMOVE** Velcro holding the Printer and **REMOVE** the power cord from the case.




3. **REMOVE** the Printer from case using the side handles.
4. **PLACE** the Printer in the Ballot Marking Touchscreen Booth to the right of the Touchscreen.
5. **RETURN** the Printer case to the Official Ballots Delivery Cart.




6. **REMOVE** the Orange Security Seal covering both the Printer and paper tray and **CHECK** that the paper inside the tray is lying flat. **PLACE** the old Orange Security Seal onto the back of the Seal Verification Form.




7. **PLACE** a new Orange Security Seal on both the Printer and paper tray ensuring the paper tray cannot be opened.




1. **CONNECT** the Touchscreen power cord (marked **orange**) to the base of the Ballot Marking Touchscreen.




2. **CONNECT** the Printer power cord (marked **green**) to the back of the Printer.
3. **PLUG** both the Printer and the Ballot Marking Touchscreen into the surge protector.



4. **CONNECT** the end of Printer cable (marked **red**) to the top port of the Printer with the USB icon (eg. ⚡) beside it .



5. **PRESS** the power button on the front side of the Printer.



SEAL VERIFICATION FORM

LOCATION: 1234 MAIN STREET
CITY

VC000001
ELECTION NAME: MMDDYYYY

RED SECURITY SEAL 2 PERSON RULE

1. **VERIFY** that the Red Security Seal serial number matches the Ballot Marking Touchscreen and this form.

- If the serial numbers **DO NOT** match or if the seal is compromised or tampered, **CALL** the Registrar of Voters Election Worker Hotline immediately.
- If the Ballot Marking Touchscreen does not power on automatically, **FOLLOW** instructions in Election Worker Guide.
- If necessary, **RESEAL** the Ballot Marking Touchscreen, then **RECORD** the replacement Red Security Seal number.

2. Election Workers **MUST COMPLETE** the "Verified By" section.

DAY #	RED SEAL #	REPLACEMENT#	REPLACEMENT#	WORKER 1	WORKER 2	PRINTED NAME	SIGNATURE
1	(051804)			WORKER 1	WORKER 2		
2				WORKER 1	WORKER 2		
3				WORKER 1	WORKER 2		
ELECTION DAY				WORKER 1	WORKER 2		

OPENING - BLUE SECURITY SEAL 2 PERSON RULE

1. **VERIFY** that the Blue Security Seal is intact.


- If the security seal is compromised or tampered, **CALL** the Registrar of Voters Election Worker Hotline immediately.

2. Election Workers **MUST COMPLETE** the "Verified By" section.

DAY #	VERIFIED BY
1	WORKER 1
2	WORKER 2
3	WORKER 1
ELECTION DAY	WORKER 1

7. **VERIFY** Blue Security Seal is intact. **INITIAL** section on the front of the Seal Verification Form. Be sure to follow steps on Seal Verification Form.

NOTE: Never remove any Blue Security Seal.



8. While holding the base, **ROTATE** the Ballot Marking Touchscreen upwards.
9. **VERIFY** Red Security Seal serial number matches with Seal Verification Form. Be sure to follow steps on Seal Verification Form.

SEAL VERIFICATION FORM

LOCATION: 1234 MAIN STREET
CITY

VC000001
ELECTION NAME: MMDDYYYY

RED SECURITY SEAL 2 PERSON RULE

1. **VERIFY** that the Red Security Seal serial number matches the Ballot Marking Touchscreen and this form.

- If the serial numbers **DO NOT** match or if the seal is compromised or tampered, **CALL** the Registrar of Voters Election Worker Hotline immediately.
- If the Ballot Marking Touchscreen does not power on automatically, **FOLLOW** instructions in Election Worker Guide.
- If necessary, **RESEAL** the Ballot Marking Touchscreen, then **RECORD** the replacement Red Security Seal number.

2. Election Workers **MUST COMPLETE** the "Verified By" section.

DAY #	RED SEAL #	REPLACEMENT#	REPLACEMENT#	WORKER 1	WORKER 2	PRINTED NAME	SIGNATURE
1	(051804)			WORKER 1	WORKER 2		
2				WORKER 1	WORKER 2		
3				WORKER 1	WORKER 2		
ELECTION DAY				WORKER 1	WORKER 2		

OPENING - BLUE SECURITY SEAL 2 PERSON RULE

1. **VERIFY** that the Blue Security Seal is intact.

- If the security seal is compromised or tampered, **CALL** the Registrar of Voters Election Worker Hotline immediately.


2. Election Workers **MUST COMPLETE** the "Verified By" section.

DAY #	VERIFIED BY
1	WORKER 1
2	WORKER 2
3	WORKER 1
ELECTION DAY	WORKER 1


NOTE: Rotating the Touchscreen upwards may cause it to tip over.

IF BALLOT MARKING TOUCHSCREEN DOES NOT POWER ON AUTOMATICALLY


- MAKE SURE Touchscreen power cord is firmly seated in socket.
- ENSURE the surge protector is powered on and all power cables are connected to a power source.
- If the previous steps do not work, then DO THE FOLLOWING:



1. **REMOVE** the Red Security Seal with scissors and **PLACE** the seal onto the back of the Seal Verification Form with tape.



2. **OPEN** door. **PRESS & HOLD** Power button until the button lights up green.



SEAL VERIFICATION FORM									
LOCATION 1234 MAIN STREET CITY		VC000001 ELECTION NAME - MMDDYYYY							
RED SECURITY SEAL						2 PERSON RULE			
1. VERIFY that the Red Security Seal serial number matches the Ballot Marking Touchscreen and this form. • If the serial numbers DO NOT match or if the seal is compromised or tampered, CALL the Registrar of Voters Election Worker Hotline immediately. 2. FOLLOW Touchscreen Powering On/Off instructions. • If Ballot Marking Touchscreen does not power on automatically, FOLLOW instructions in Election Worker Guide. • As necessary, RESEAL the Ballot Marking Touchscreen, then RECORD the replacement Red Security Seal number. 3. Election Workers MUST COMPLETE the "Verified By" section.									
DAY #	RED SEAL #	REPLACEMENT #	REPLACEMENT #	WORKER 1	WORKER 2	PRINTED NAME	VERIFIED BY	SIGNATURE	
1	(051804)			WORKER 1	WORKER 2				
2				WORKER 1	WORKER 2				
3				WORKER 1	WORKER 2				
ELECTION DAY				WORKER 1	WORKER 2				
OPENING - BLUE SECURITY SEAL						2 PERSON RULE			
1. VERIFY that the Blue Security Seal is intact. • If the security seal is compromised or tampered, CALL the Registrar of Voters Election Worker Hotline immediately. 2. Election Workers MUST COMPLETE the "Verified By" section.									
DAY #	WORKER 1	WORKER 2	PRINTED NAME	VERIFIED BY	SIGNATURE				
1	WORKER 1	WORKER 2							
2	WORKER 1	WORKER 2							
3	WORKER 1	WORKER 2							
ELECTION DAY	WORKER 1	WORKER 2							

3. **CLOSE** door and **SECURE** with a new Red Security Seal. **WRITE** new Red Security Seal number on the front of the Seal Verification Form. Be sure to follow steps on Seal Verification Form.
4. **CALL** Election Worker Hotline (510) 835-7205 to notify them that the seal was replaced.

OPENING POLLS

DAILY

DAILY


DAILY

DAILY


DAILY




1. **INSERT** the Poll Worker Card into the yellow slot at the bottom of the Ballot Marking Touchscreen with the gold chip facing up and toward the Touchscreen.




2. **ENTER** the Administrator Login number found on the Touchscreen Codes List in the Operations Sleeve on the left-hand side of the booth. **PRESS** "Login" then Administrative Mode will begin.




3. **CONFIRM** the "AVS Controller" and "Manual Session Activation" checkboxes (marked orange) are both selected.
4. **PRESS** the "Hardware Test" button (marked blue).




5. **SELECT** the "ATI" button on screen to proceed.



6. **PRESS** each button on the ATI device to verify the buttons work. The green checkmarks will indicate that the button is responding. **PRESS** "Back to Menu" when finished.




7. **SELECT** the "Sound test" button on screen to proceed.



8. The green checkmark and the words "Audio headphones connected" will indicate that the headphones are functioning. While listening to the headphones, **PRESS** the "Play" symbol to check the sound functionality. **PRESS** "Back to Menu" when finished.




9. **SELECT** the "Printer" button on screen to proceed.




10. **PRESS** "Print test page" button to print a test page verifying the Printer is connected properly. Once the test page prints, **SPOIL** the test page by placing into Purple Spoiled Ballots Bag. **PRESS** the Close button when finished.

NOTE: If a Test Page does not print, **DOUBLE CHECK** the Printer's connections to the surge protector and Ballot Marking Touchscreen, and that the paper is lying flat.



11. **CONFIRM** the Public Counter is "0" (marked orange).
12. **PRESS** "Open Polls" button (marked blue).



13. **PRESS** "Yes" to confirm opening of the polls on the Ballot Marking Touchscreen.



14. **REMOVE** the Poll Worker Card from the Ballot Marking Touchscreen. The Poll Worker Card must be with the Demonstration Officers for use throughout the day.

ELECTION DAY

ELECTION DAY

1ST VOTER PROCEDURE

DAILY

DAILY

DAILY

DAILY

DAILY

The first Voter (either Vote by Mail or in-person) to enter the Vote Center will be processed at the Official Table, but will not be given a Ballot or activate a Ballot Marking Touchscreen Ballot until 1st (first) Voter Procedure is complete.

The first Voter must not be an Election Worker.

1. **VOTER VERIFIES** all Ballot Marking Touchscreens “Total ballots printed” read zero (0).
2. **VOTER VERIFIES** all Red Security Seals on the Ballot Marking Touchscreens rear, lower back panel is sealed closed.
3. **VOTER VERIFIES** all Blue Security Seals on the Ballot Marking Touchscreens rear, upper back panel is sealed closed.
4. **VOTER CONFIRMS** the following are empty:
 - Yellow Vote By Mail Ballots Trolley
 - Blue Provisional Ballots Trolley
 - Turquoise Official Ballots Bag (including bin)
5. **PLACE** the bin inside the Turquoise Official Ballots Bag (*as seen on image right*). **ZIP** the top flap closed. **ENSURE** the back flap is also zipped closed.
6. **THE DEMONSTRATION OFFICER CLOSES & SECURES** each Trolley/ Bag with a White Security seal.
7. **PROCESS VOTER**, if Voter is voting in person.



THE OFFICIAL TABLE: INTRODUCTION

KNOW THE ROLES:



Captain



Assistant Captain



Poll Pad Operator



Demonstration Officers



BOD Operator



BREAK SCHEDULE

Breaks and lunch/dinner breaks will be broken into thirds and managed on the Break Schedule sheets (as pictured below). Only three (3) people will be allowed to go on breaks and lunch/dinner breaks at a time to cover all positions.

Break schedule timeline will be as follows:

EARLY VOTING DAYS

15-MINUTE BREAK: 10:00 AM, 10:30 AM, 11:00 AM

LUNCH: 11:30 AM, 12:30 PM, 1:30 PM

15-MINUTE BREAK: 2:30 PM, 3:00 PM, 3:30 PM

ELECTION DAY

15-MINUTE BREAK #1: 8:00 AM, 8:30 AM, 9:00 AM

1-HOUR LUNCH: 9:30 AM, 10:30 AM, 11:30 AM

15-MINUTE BREAK #2: 12:30 PM, 1:00 PM, 1:30 PM

1-HOUR DINNER: 2:30 PM, 3:30 PM, 4:30 PM

15-MINUTE BREAK #3: 5:30 PM, 5:45 PM, 6:00 PM

ALAMEDA COUNTY REGISTRAR OF VOTERS

CAPTAIN: Try to incorporate Election Workers' Preferences as you complete the schedule. Arrange for orderly breaks.

Election Workers receive one (1) one-hour break.

Early Voting Break Schedule - Date: _____

Election Workers	1st Break			Lunch			2nd Break		
	8:00 AM - 8:30 AM	8:30 AM - 9:00 AM	9:00 AM - 9:30 AM	11:30 AM - 12:00 PM	12:00 PM - 12:30 PM	12:30 PM - 1:00 PM	1:30 PM - 2:00 PM	2:00 PM - 2:30 PM	2:30 PM - 3:00 PM
Captain:									
Judge:									
Judge:									
Judge:									
Clerk:									
Clerk:									
Clerk:									


ALAMEDA COUNTY REGISTRAR OF VOTERS

CAPTAIN: Try to incorporate Election Workers' Preferences as you complete the schedule. Arrange for orderly breaks.

Election Workers receive two (2) one-hour breaks.

Election Day Break Schedule

Election Workers	1st Break			Lunch			2nd Break			3rd Break		
	8:00 AM - 8:30 AM	8:30 AM - 9:00 AM	9:00 AM - 9:30 AM	11:30 AM - 12:00 PM	12:00 PM - 12:30 PM	12:30 PM - 1:00 PM	1:30 PM - 2:00 PM	2:00 PM - 2:30 PM	2:30 PM - 3:00 PM	3:00 PM - 3:30 PM	3:30 PM - 4:00 PM	
Captain:												
Judge:												
Judge:												
Judge:												
Clerk:												
Clerk:												
Clerk:												



NOTE: Trolleys must be close to Election Workers at all times.

ATTENTION ALL ELECTION WORKERS!

The following guidelines are intended to help you on Election Day and help us maintain a good working relationship with all of our Vote Center organizers.

PLEASE REMEMBER: The manner in which you communicate with the Vote Center organizers directly affects whether or not we are able to continue using a facility. Please show consideration for the person(s) allowing us to use their facility. Please keep the following suggestions in mind on Election Day when you are working at the Vote Center.

- Election Workers are not allowed to bring children to the Vote Center.
- We are guests in the Vote Center facility. The Captain should familiarize themselves with the rules. Use tape carefully on the walls or woodwork so that you do not permanently damage the facility. If in doubt, ask first.
- Be polite to the other occupants sharing the space. If major problems occur, call the Registrar of Voters' Office.
- Bilingual Election Workers are present in order to assist the language communities. The Bilingual Election Workers are placed in each Vote Center based on the number of language Voters in that area. Any missing Bilingual Election Worker must be replaced.
- Do not move large furniture without permission.
- The Vote Center organizers are not required to give Election Workers access to bathroom facilities, telephones, and kitchens. If they are offered, please keep them neat. If they are not available, please make other arrangements.
- All Election Workers are an extension of the Registrar of Voters' Office. The manner in which you perform your duties is a direct reflection of our office.
- Election Workers must be dressed in appropriate business casual attire.
- Use of cell phones while serving is STRICTLY PROHIBITED. Please use while on break only.
- Discussion about the election or any political topic is STRICTLY PROHIBITED. If this becomes an issue, call the Registrar of Voters' Office.
- Eating at the Voting area and the Official table is STRICTLY PROHIBITED.

NOTE:

- Cleaners from vendor companies, and any other non-election workers who may be present in the facility, must not be asked to assist with any election duties. This includes moving voting equipment, handling election materials, or participating in voter check-in. Only trained Election Workers may perform election operations.
- Poll Pads must only be used to look up voters who are physically present at the Vote Center to vote. Election Workers must not use Poll Pads to search for neighbors, friends, or any individuals who are not currently checking in to vote.
- All Election Workers must follow the Election Worker Guide to protect voter privacy and maintain secure, professional operations.
- Personal cell phones and tablets may not be used at the Official Table(s) or Demonstration Officer table.
- Captains and Assistant Captains should remind Election Workers of proper etiquette and Poll Pad procedures throughout the day.

THANK YOU FOR SERVING AS AN ELECTION WORKER!

The purpose of these guidelines is to effectively manage voter lines and flow while ensuring accessibility, voter privacy, and the protection of Voters rights.

NOTE: Captain will assign available Election Workers as Line Monitors.

1. ASK VOTER:

“Are you here to drop off your Vote by Mail Ballot?”

If yes: DIRECT VOTER to the Demonstration Officer by the Yellow Vote by Mail Ballots Trolley.

If no: PROCEED to the next question.

2. ASK VOTER:

“Are you registered to vote in Alameda County?”

If yes (voting in-person or in-person VBM): DIRECT VOTER to remain in line.

If no (a Voter needs to register or resolve registration-related issues using the Conditional Provisional Registration Form (CPR) or Registration Process):

- **OFFER VOTER** CPR or Registration form. **INSTRUCT** Voter to complete the form as required.
- **INFORM VOTER** that further assistance will be available at the Poll Pad Operator Table.
- **DIRECT VOTER** to the other Poll Pad line (if applicable). This line can be focused on Conditional/Provisional voters, and can also be used to process regular voters if there are no Conditional/Provisional voters.

NOTE:

- **MANAGE** the Voter line.
- **COMMUNICATE** with Voters.
- **KEEP** the line organized and entrances and accessible pathways clear.
- **DIRECT** Voters to the appropriate place as space becomes available.
- **HELP** prevent crowding around the entrance and Official Table.
- **MONITOR** for Voters who may need assistance.
- **COMMUNICATE** Voter flow, delays, and assistance needs to the Captain.



OFFICIAL TABLE POLL PAD OPERATOR

OFFICIAL TABLE POLL PAD OPERATOR



“Good morning/afternoon!”

We would like to inform you that Facsimile Reference Ballots and language assistance are available, and if we can help you in any way, kindly let us know.”

IF VOTER DECLINES

PROCEED to locate Voter on the Poll Pad.

IF VOTER REQUESTS ASSISTANCE

1. **ASK VOTER:**
“How can I be of assistance?”
2. On the Poll Pad, **MARK** the Voter as “Assistance Required” and **SELECT** the reason.

IF VOTER NEEDS LANGUAGE ASSISTANCE:

1. **ASK** Bilingual Election Worker who speaks the same language to help Voter.
In case no Bilingual Election Workers are present, USE Captain Cell Phone to call Language Hotline for assistance (refer to Cell Phone contacts on back page of Election Worker Guide). PROVIDE the Language Hotline with the Voter's precinct and Ballot Type to further assist.

IF VOTER WITH DISABILITY REQUESTS ASSISTANCE:

1. **DO NOT ASK** about or mention a Voter's disability.
2. Etiquette Guidelines regarding **Disability Sensitivity at the Polls** are available in the Election Worker Guide.
3. **FACILITATE** assistance from other Election Workers.


IF VOTER REQUESTS A FACSIMILE REFERENCE BALLOT:

1. **PROCESS** the Voter. NOTIFY the BOD Operator to print a requested language Facsimile Reference Ballot, if available.
2. **INFORM VOTER** that they may use the Ballot as a reference to assist them with marking their Official Ballot.

IF VOTER NEEDS AMERICAN SIGN LANGUAGE (ASL) ASSISTANCE:

1. **CONTACT** the Election Worker Hotline, (510) 835-7205, for a resolution.

FACSIMILE REFERENCE BALLOTS



Available in all Vote Centers, as required per Election Code, Section 14201, Facsimile Reference Ballots are provided in languages that Official Ballots are not available in.


Facsimile Reference Ballots are a translated version of the Official Ballot used to aid the Voter in marking the Official Ballot.

Facsimile Reference Ballots are printed and provided by the BOD Operator.


IF THE LANGUAGE REQUESTED IS NOT AVAILABLE:

USE Captain Cell Phone to call Language Hotline for assistance (*refer to Cell Phone contacts on back page of Election Worker Guide*). **PROVIDE** the Language Hotline with the Voter's precinct and Ballot Type to further assist.

TASK 2 PROCESSING VOTER




1. **PRESS** "Get Started" to locate the Voter by using their first and last name.




2. **USE** the on-screen keyboard to enter the first three (3) letters of the voter's last and first name, then **PRESS** "Search".


NOTE: To narrow search results, **USE** "ADVANCED OPTIONS".



3. Records matching the search criteria display on-screen. The Voter's record may contain a status that reads "VBM Ballot Sent" because all registered Voters will receive a VBM Ballot this Election. **SELECT** the Voter by touching their record.



4. The Poll Pad will display instructions on how to assist the Voter. **PRESS** "CONTINUE" to proceed.



5. If "Vote by Mail Ballot Issued" prompt appears above the Voter's information, **VERIFY** if the Voter does or does not have VBM materials to surrender. **ASK VOTER**, "Would you like to vote your Vote by Mail Ballot in person?"
If yes, CONTINUE following this process until the completion of step 8.
If no, CONTINUE following this process to the end. **PRESS** "CONTINUE" to proceed.

- 6. ROTATE** the Poll Pad to the Voter to confirm their information is correct. **INFORM VOTER** to press “ACCEPT” if their information is correct. **If the Voter’s address or party information is incorrect**, refer to pg. 104 to update information. **If the Voter’s information is incorrect**, refer to pg. 106 to change information.

NOTE: PRESS “SPEAK” to play audio of the Voter’s information through Poll Pad speakers only when necessary or requested by the Voter.

- 7. INFORM VOTER** to select their Ballot Language option then **PRESS** “ACCEPT” to continue. **If Voter who needs assistance is visually impaired, ASSIST** the Voter in selecting their Ballot Language option.

- 8. INFORM VOTER** to sign the Oath on the Poll Pad and press “DONE SIGNING” to continue. **ROTATE** the Poll Pad to face the Operator. **If Voter previously indicated (in step 5) that they would like to vote their Vote by Mail Ballot in person, PROCEED** to “IN-PERSON VBM VOTER” scenario (pg. 95).

NOTE: PRESS “SPEAK” to play audio of the Voter’s information through Poll Pad speakers only when necessary or requested by the Voter.



NOTE: PRESS “LISTEN TO OATH” to play audio of oath through Poll Pad speakers only when necessary or requested by the Voter.

If Voter who needs assistance is visually impaired, a Signature Guide is available for Poll Pad use, found in the Official Table Supply Box. **SLIDE** Poll Pad signature guide on top of the screen to assist with signing.

TASK 2 PROCESSING VOTER

Alameda County
Alameda County Courthouse

POLL WORKER CONFIRMATION START OVER SUBMIT

CONFIRM THE VOTER'S INFORMATION

GEORGE WASHINGTON
101 MAIN ST, ALAMEDA, CA, 94501
Precinct: 101 DOB: 07/04/1976
Status: Active Voter ID: 97500003

Declared Party: Democratic
Ballot Style: DEM-0006 English

Signature on Election Day

Voting Method: VBM, Paper, Electronic

9. **ASK VOTER**, "Would you like to vote on the Ballot Marking Touchscreen?"
If yes, **SCROLL DOWN** the list to **SELECT** "Electronic" under "Voting Method".
If no, **SELECT** "Paper", then **PRESS** "SUBMIT".



10. This screen will indicate that the Voter has been successfully processed.



11. Once Voter is successfully processed, a Ballot Form will print out. The Ballot Form will inform either the BOD Operator or Demonstration Officer the Voter's Precinct number, Ballot Type, and Language Preference.

NOTE: The Ballot Form **CANNOT** be reprinted.
LOOK UP the Voter's name again to retrieve Precinct number, if necessary.

PAPER BALLOT VOTER

GIVE the Ballot Form directly to the Ballot On Demand (BOD) Operator. **INFORM** the Voter to proceed to the BOD Operator as their Ballot card(s) print(s).

TOUCHSCREEN VOTER

GIVE the Ballot Form and Secrecy Sleeve to the Voter. **INFORM** the Voter to give the form to one of the Demonstration Officers to activate their Ballot. **REMAND** the Voter that the Secrecy Sleeve is used to keep their printed Ballot private as they deposit it into the Turquoise Official Ballots Bag.

IN-PERSON VBM VOTER

NOTE: A Voter may carry in the Official Ballot they received in the mail, check in, and cast it without using the return envelope.



1. **GIVE VOTER** a Secrecy Sleeve and pen.
INFORM VOTER to place their Vote by Mail Ballot cards in the Secrecy Sleeve, covering their selections, but with the top portion visible.
2. **CONFIRM** that the election name and date printed on the ballot cards are for this election. Only cards from this election can be deposited in the Turquoise Official Ballots Bag.
3. **VERIFY** that the Voter has brought the correct precinct ballot by checking the voter's information on the Poll Pad.

Alameda County
1ST CONGREGATIONAL
CHURCH OF ALAMEDA

GO BACK

If Voter Needs Assistance

WASHINGTON, GEORGE
DOB: 07/04/1976 - Party: Democratic
101 MAIN ST, ALAMEDA, CA, 94501
Precinct 101

CONTINUE

IF VOTER NEEDS LANGUAGE ASSISTANCE:
1. ASK Bilingual Election Worker who speaks the same language to help Voter. In case of no Bilingual Election Workers present, USE Inspector Cell Phone to call Language Hotline for assistance. Refer to Cell Phone contacts on back page of Election Worker Guide.

IF VOTER WITH DISABILITY REQUESTS ASSISTANCE:
1. DO NOT ASK about or mention a Voter's disability.
2. Etiquette Guidelines regarding Disability Sensitivity at the Polls are available in the Election Worker Guide.
3. FACILITATE assistance from other Election Workers.

NOTE:**IF THE VOTER HAS THE WRONG PRECINCT NUMBER ON BALLOT:**

1. **INFORM VOTER:** "This Ballot isn't for your assigned precinct, so we need to issue you the correct precinct Ballot."
2. **OFFER VOTER** a paper or Touchscreen Ballot. **FOLLOW** the regular paper or Touchscreen procedures.

BOD Officer Ballot Cards Index

#	Precinct	Ballot Type	Card Count
1	200100	BT013	6
2	200200	BT013	6
3	201400	BT013	6
4	202200	BT013	6
5	202500	BT011	6
6	202620	BT011	6
7	203100	BT012	6
8	203500	BT012	6
9	203800	BT012	6
10	203880	BT012	6
11	203890	BT012	6
12	204210	BT012	6
13	204510	BT013	6
14	204900	BT011	6
15	205200	BT013	6
16	205700	BT013	6
17	206200	BT013	6
18	206900	BT010	6
19	207000	BT013	6
20	207200	BT009	6
21	207700	BT010	6
22	208010	BT010	6
23	208300	BT013	6
24	208510	BT013	6
25	208600	BT012	6
26	208800	BT013	6

4. **CONFIRM** the Voter has the correct number of card(s) using the Ballot Card Index.

NOTE: The Ballot size for this election is 8.5 inches by 16 inches.

IN-PERSON VBM VOTER (cont.)

Alameda County
Alameda County Courthouse

POLL WORKER CONFIRMATION

START OVER SUBMIT

CONFIRM THE VOTER'S INFORMATION

GEORGE WASHINGTON
101 MAIN ST, ALAMEDA, CA, 94501
Precinct: 101 DOB: 07/04/1976
Status: Active Voter ID: 97500003

Declared Party: Democratic
Ballot Style: DEM-00006 English

Signature on Election Day

Assistance Required Curbside

Voting Method

VBM
Paper
Electronic

5. If the Voter has the correct number of cards, **SCROLL DOWN** the list to SELECT “VBM” under “Voting Method”.
PRESS “SUBMIT” - the screen will indicate the Voter is “Processed Successfully”.



6. The Ballot Form will print.
7. If the Voter needs to mark their in-person VBM Ballot, **DIRECT VOTER** to a Voting Booth.
If the Voter is ready to cast their in-person VBM Ballot, **DIRECT VOTER** to a Demonstration Officer to cast their ballot in the Turquoise Official Ballots Bag. The Demonstration Officer will check that the Voter is depositing only one set of ballot cards.
8. If the Voter does not require additional assistance, **SPOIL** the Ballot Form. If the Voter needs any additional assistance, **GIVE** the Ballot Form to the BOD Operator to be used in printing a VIG or Facsimile Ballot then **DIRECT VOTER** to BOD Operator.

THE VOTER HAS AN INCORRECT NUMBER OF CARDS (correct precinct number):

IF THERE ARE DUPLICATE CARDS:

1. **INFORM VOTER** that they may legally vote only one set of Ballots. **ASK VOTER** to choose one set of Ballot Cards—without any duplicates—that they wish to use. **OFFER** to take the duplicate card(s), **WRITE** “VOID” on them, and place them in the Gray Voided/Surrendered Vote by Mail Ballots Bag.
2. After the Voter has chosen one set of Ballot Cards to use, **SCROLL DOWN** the list on the Poll Pad to **SELECT** “VBM” under “Voting Method”. **PRESS** “SUBMIT” - the screen will indicate the Voter is “Processed Successfully”. The Ballot Form will print. If the Voter needs to mark their in-person VBM Ballot, **DIRECT VOTER** to a Voting Booth. If the Voter is ready to cast their in-person VBM Ballot, **DIRECT VOTER** to a Demonstration Officer to cast their ballot in the Turquoise Official Ballots Bag. The Demonstration Officer will check that the Voter is depositing only one set of ballot cards.
3. **If the Voter is unable to choose one set of Ballot Cards to vote, PRESS** “START OVER” to cancel the process.

IF LESS THAN THE FULL AMOUNT:

GIVE VOTER the following options:

- a. **CAST** their Ballot as is.
If the Voter chooses this option, SCROLL DOWN the list on the Poll Pad to **SELECT** “VBM” under “Voting Method”. **PRESS** “SUBMIT” - the screen will indicate the Voter is “Processed Successfully”. The Ballot Form will print. If the Voter needs to mark their in-person VBM Ballot, **DIRECT VOTER** to a Voting Booth. Once the Voter is ready to cast their in-person VBM Ballot, **DIRECT VOTER** to a Demonstration Officer to cast their ballot in the Turquoise Official Ballots Bag. The Demonstration Officer will check that the Voter is depositing only one set of ballot cards.
- b. **OFFER** a paper Ballot.
If the Voter chooses a paper Ballot, INFORM VOTER: “Since some of your Ballot cards are missing, we can take the Vote by Mail Ballot you have and issue you a new set.” **WRITE** “VOID” on the Voter’s existing ballot cards and place them in the Gray Voided/Surrendered Vote by Mail Ballots Bag. **SCROLL DOWN** the list on the Poll Pad to **SELECT** “Paper” under “Voting Method”. **PRESS** “SUBMIT” - the screen will indicate the Voter is “Processed Successfully”. The Ballot Form will print. **GIVE** the Ballot Form directly to the Ballot On Demand (BOD) Operator. **INFORM VOTER** to proceed to the BOD Operator as their new set of Ballot card(s) print(s)
- c. **OFFER** a Touchscreen Ballot
If the Voter chooses a Touchscreen ballot, OFFER to take the existing Vote by Mail Ballot card and **WRITE** “VOID” on the Voter’s existing Vote by Mail ballot cards and place them in the Gray Voided/Surrendered Vote by Mail Ballots Bag. **SCROLL DOWN** the list on the Poll Pad to **SELECT** “Touchscreen” under “Voting Method”. **PRESS** “SUBMIT” - the screen will indicate the Voter is “Processed Successfully”. The Ballot Form will print. **INFORM VOTER** to give the form to one of the Demonstration Officers to activate their Ballot. **REMAND VOTER** that the Secrecy Sleeve is used to keep their printed Ballot private as they deposit it into the Turquoise Official Ballots Bag.

VOTE BY MAIL VOTERS

SURRENDERING VBM BALLOT TO VOTE



NOTE: It is **not required** for Voters to surrender their Vote by Mail Ballot.



1. **WRITE "VOID"** on VBM Envelope and **PARTIALLY TEAR**.
2. **PLACE** Voided VBM into **Gray Voided/Surrendered VBM Ballots Bag**. **CONTINUE** processing Voter.

REPLACEMENT VBM ENVELOPE

1. **GIVE VOTER** Official Vote by Mail Replacement envelope and Pen.
2. **INFORM VOTER** to fill out back of the envelope completely. The VBM Replacement envelope is for a complete set of Ballot Card(s).



VBM VOTER SCENARIOS

IF A VBM VOTER SUBMITS AN RAVBM (REMOTE ACCESS VOTE BY MAIL) BALLOT:

- **INFORM VOTER** to double check that they have their printed Ballot and the required documents (Vote Oath and Voter Return Envelope Form) containing their signature. They can submit into the Yellow Trolley with their provided envelope or a replacement envelope.
- **If the Voter needs a replacement envelope for their RAVBM Ballot**, the Voter can use a replacement VBM Envelope.

IF A VBM VOTER NEEDS (USING VBM ENVELOPE) A CARD REPLACED:

- **VOID & SURRENDER** the remaining card(s). Then **PROCESS** the Voter to vote in-person.

Alameda County
Alameda County Courthouse

POLL WORKER CONFIRMATION

START OVER SUBMIT

CONFIRM THE VOTER'S INFORMATION

GEORGE WASHINGTON
9769 CHELLS DR, ALAMEDA, CA 94501
Precinct: 101 DOB: 12/31/1969
Status: Active Voter ID: 97500003

Signature on Election Day

Ballot Style: English 101-1

☒ Assistance Required ☐ Curbside

Voting Method

1. If the Voter requests assistance, **SELECT** the Voting Method first, then “Assistance Required”.

Assistance Required

Select what assistance was given to voter and sign below

CHOOSE REASON

Accessibility

Marking the Ballot

Language Assistance - Burmese

Language Assistance - Chinese

Language Assistance - Hindi

Language Assistance - Khmer

Language Assistance - Korean

Language Assistance - Laotian

Language Assistance - Mien

Language Assistance - Mongolian

Language Assistance - Punjabi

CLEAR SIGNATURE

2. A pop-up window will appear. **SELECT** one of the listed reasons for assistance from the drop-down menu:

- Accessibility
- Marking the Ballot
- Language Assistance — [Language]
- Facsimile Ballot — [Language]

Assistance Required

Select what assistance was given to voter and sign below

ACCESSIBILITY

CLEAR SIGNATURE

Signature on Election Day

3. **THE ELECTION WORKER SIGNS** after reason for assistance has been selected. PRESS “CONTINUE” to proceed.

Alameda County
Alameda County Courthouse

POLL WORKER CONFIRMATION

START OVER SUBMIT

CONFIRM THE VOTER'S INFORMATION

GEORGE WASHINGTON
9769 CHELLS DR, ALAMEDA, CA 94501
Precinct: 101 DOB: 12/31/1969
Status: Active Voter ID: 97500003


Signature on Election Day

Ballot Style: English 101-1

☐ Assistance Required ☒ Curbside

Voting Method

4. **For Curbside Voters, SELECT** the Voting Method first, then “Curbside”. **Curbside Voters can only vote on Paper.**



1. **If the voter qualifies as a Youth Voter**, it means they are younger than 18 but still have the right to vote in specific races depending on the jurisdiction.

These Youth Voters will be assigned ballot types that end with the suffix “YV” and their precinct numbers will conclude with the letter “Y,” such as 200100Y.

2. **If a Youth Voter is unregistered**, proceed to “CONDITIONAL VOTER – YOUTH VOTER” section (*proceed to pg. 106*).

VOTER ID REQUIRED

5:30 PM Thu Oct 8 Training Data Election 10/7/2020
TRAINING MODE Last Imported: 11/03/2020

Alameda County
ALAMEDA HIGH SCHOOL

GO BACK

ID REQUIRED

HARRISON, WILLIAM HENRY
02/09/1903
1019 VIA GRANADA, LIVERMORE, CA 94550
Precinct 501410

ID Required - Voter must provide one of the Valid ID's listed in the H.A.V.A. ID requirements found in the Election Worker Guide.

Select **SHOWED CORRECT ID** button on the right to proceed.

If voter unable to provide Valid ID. Select **CLOSE** and process as provisional voter.

SHOWED CORRECT ID
UNABLE TO SHOW CORRECT ID
CLOSE

1. After selecting the Voter, it may indicate "ID REQUIRED". The Voter is required to show Valid ID (a list of acceptable IDs can be found in the HAVA ID Requirements Binder).
2. SELECT "SHOWED CORRECT ID", if Voter is able to provide the correct identification.

If the Voter cannot provide ID, SELECT "UNABLE TO SHOW CORRECT ID" and **PROCESS** the Voter Provisionally. **WRITE DOWN** the Voter's Precinct Number on the Conditional Provisional Registration (CPR) Form (proceed to pg. 106).

NOTE: Election Workers must not ask a voter to provide their identification unless the Poll Pad states identification is needed.

VOTER INACTIVE

5:38 PM Thu Oct 8 Training Data Election 10/7/2020
TRAINING MODE Last Imported: 11/03/2020

Alameda County
ALAMEDA HIGH SCHOOL

Precinct Records: 30000
Checks: 0

LINCOLN First Name Search ADVANCED OPTIONS

SEARCH RESULTS: 6

LINCOLN, ABRAHAM 02/12/1909 22 BRET HARTE RD, BERKELEY, CA 94708 VOTER ID: 76500010	Inactive	Precinct: 200100
LINCOLN, BODIE 10/25/1962 1327 BRECKENRIDGE ST, SAN LEANDRO, CA 9457900...	VBM Ballot Sent	Precinct: 450200
LINCOLN, HADLEIGH 09/22/1994 2746 WINCHESTER DR, HAYWARD, CA 94541 VOTER ID: 76517578	VBM Ballot Sent	Precinct: 491300
LINCOLN, HARMONY 08/25/1924 3206 ENCINAL AVE, ALAMEDA, CA 945014805 VOTER ID: 76526267	Inactive	Precinct: 301200

1. Records matching the search criteria display on-screen. If Voter's record contains a status that reads "Inactive", SELECT the Voter by touching their record to continue.
2. The Poll Pad will display instructions on how to assist the Voter. **PRESS** "CONTINUE" to proceed.

5:38 PM Thu Oct 8 Training Data Election 10/7/2020
TRAINING MODE Last Imported: 11/03/2020

Alameda County
ALAMEDA HIGH SCHOOL

GO BACK

Inactive Voter

LINCOLN, ABRAHAM
02/12/1909
22 BRET HARTE RD, BERKELEY, CA 94708
Precinct 200100

Follow CPR instructions in the Election Worker Guide.

3. A prompt below the Voter's name will display with instructions on how to process the voter.
- If the Voter chooses to vote at the Vote Center, **WRITE DOWN** the Voter's Precinct Number on the CPR Form, **SELECT** "GO BACK" and **PROCESS** the Voter Provisionally (proceed to pg. 109).

VOTER ALREADY VOTED – VOTER BALLOT RECEIVED

VOTER ALREADY VOTED

Training Data Election 10/7/2020
TRAINING MODE Last Imported: 11/03/2020

Alameda County
ALAMEDA HIGH SCHOOL

Precinct Records: 30000
Checks: 1

WASHINGTON GEORGE Search ADVANCED OPTIONS

SEARCH RESULTS: 1

WASHINGTON, GEORGE
12/31/1969
2717 MONTEREY BLVD, OAKLAND, CA 94602
VOTER ID: 76500008

Voted Precinct: 245100
Ballot Type: 19 English
CHK: 10/06/2020, 17:33:59

1. If the Voter's record contains a status that reads **"Voted"** with the Voter's signature and time stamp, **SELECT** the Voter by touching their record to continue.
2. The Poll Pad will display instructions on how to assist the Voter. **PRESS** "CONTINUE" to proceed.

Training Data Election 10/7/2020
TRAINING MODE Last Imported: 11/03/2020

Alameda County
ALAMEDA HIGH SCHOOL

Precinct Records: 30000
Checks: 1

WASHINGTON GEORGE Search ADVANCED OPTIONS

SEARCH RESULTS: 1

WASHINGTON, GEORGE
12/31/1969
2717 MONTEREY BLVD, OAKLAND, CA 94602
Precinct 245100

Voted Precinct: 245100
Ballot Type: 19 English
CHK: 10/06/2020, 17:33:59

3. A prompt below the Voter's name will display with instructions on how to process the voter.
If the Voter chooses to vote at the Vote Center, WRITE DOWN the Voter's Precinct Number on the CPR Form, **SELECT** "GO BACK" and **PROCESS** the Voter Provisionally (*proceed to pg. 109*).

VOTER HAS RETURNED A VBM BALLOT

Training Data Election 10/7/2020
TRAINING MODE Last Imported: 11/03/2020

Alameda County
ALAMEDA HIGH SCHOOL

Precinct Records: 30000
Checks: 1

MADISON JAMES Search ADVANCED OPTIONS

SEARCH RESULTS: 1

MADISON, JAMES
03/16/1901
4015 ELSTON AVE, OAKLAND, CA 94602
VOTER ID: 76500013

Voted Precinct: 224500

1. If the Voter's record contains a status that reads **"Voted"**, **SELECT** the Voter by touching their record to continue.
2. The Poll Pad will display instructions on how to assist the Voter. **PRESS** "CONTINUE" to proceed.

Training Data Election 10/7/2020
TRAINING MODE Last Imported: 11/03/2020

Alameda County
ALAMEDA HIGH SCHOOL

Precinct Records: 30000
Checks: 1

MADISON JAMES Search ADVANCED OPTIONS


SEARCH RESULTS: 1

MADISON, JAMES
03/16/1901
4015 ELSTON AVE, OAKLAND, CA 94602
Precinct 224500


Voted Precinct: 224500

3. A prompt below the Voter's name will display with instructions on how to process the voter.
If the Voter chooses to vote at the Vote Center, WRITE DOWN the Voter's Precinct Number on the CPR Form, **SELECT** "GO BACK" and **PROCESS** the Voter Provisionally (*proceed to pg. 109*).

VOTER NOT FOUND



1. If the Voter cannot be found, a pop-up displays: No Records Found. **PRESS** “OK” to go back to VOTER LOOKUP.



2. From the VOTER LOOKUP screen, **PRESS** the “ADVANCED OPTIONS” button.
3. **LOOK UP** the Voter by using DOB (DATE OF BIRTH) or ADDRESS. **PRESS** “DONE” on the keyboard, then Search.
 - If Voter’s information is found using “ADVANCED OPTIONS”, **FOLLOW** same process a Regular Voter.
 - If Voter’s information is **NOT** found using “ADVANCED OPTIONS”, **FOLLOW** Conditional Voter procedures.

CONFIDENTIAL VOTER

Some Voters have a confidential status for safety or privacy reasons. This may include candidates running for office. Because of this:

- They will not appear on the Poll Pad, and their information is not visible to Election Workers.
- They cannot vote as a regular in-person Voter.
- They also cannot vote as an in-person VBM Voter.
- However, they can deposit their completed Vote by Mail Ballot and envelope into the Yellow Vote by Mail Ballots Trolley.
- They also may vote using the Conditional Voter process, but may lose their confidential status.

If a person states they are a Confidential Voter, **CONTACT** the Election Worker Hotline, (510) 835-7205 for guidance.

UPDATE VOTER ADDRESS/PARTY

Alameda Training Election
TRAINING MODE (Last Imported: 06/07/2022)

Alameda County
Alameda County Courthouse

VOTER CONFIRMATION GO BACK ACCEPT

Verify voter information and tap accept to continue

SPEAK **GEORGE WASHINGTON**
DOB: 12/31/1969
9769 CHELLS DR, ALAMEDA, CA 94501

Voter ID: 97500003 Status: Active Precinct: 101

Registration

1. If the Voter's address information/Party Preference needs to be updated, PRESS "Update Registration Info".

If the Voter wants to change their name, PROCESS Voter Conditionally (*proceed to pg. 106*).

Previous Step Update Party Preference X

Scan 1 2 3 Next

Enter Voter Information

NO PARTY PREFERENCE

Party

- American Independent
- Democratic
- GREEN
- Libertarian
- NO PARTY PREFERENCE
- Peace and Freedom
- Republican

* Indicates a required field

2. SELECT the Voter's Party Preference from the drop-down menu. PRESS "Next" to proceed.

Previous Step Update Residence Address X

Address Type 1 2 3 Next

2717 MONTEREY BLVD
House # * Suffix Pre Direction Street Name * Street Type Post Direction

OAKLAND CA 94602
Unit Type Unit Number City * State * Zip *

CLEAR FORM Same Mailing Address YES NO

* Indicates a required field

3. UPDATE the Voter's address. The Voter's address will automatically populate. SELECT the appropriate answer for Same Mailing Address.

If applicable, ENTER Voter's Mailing Address. PRESS "Next" to proceed.

Previous Step Jurisdiction Details X

1 2 3 4 Next

Address not found. EXIT and process as Conditional Voter.

Precinct


Split

* Indicates a required field


If Voter is active registered voter and their updated address is not found, Voter will have to vote Provisionally (*pg. 109*).

If Voter is not in the system and the address is not found, Voter will have to vote Conditionally (*pg. 106*).

CONTACT the Election Worker Hotline for assistance locating Precincts for hard-to-locate addresses. PRESS "Next" to proceed.




4. **ROTATE** the Poll Pad to face the Voter. The Voter must confirm that the changes are correct. **If the Voter who needs assistance is visually impaired, ASSIST** the Voter in confirming that the changes are correct.



5. **VOTER SIGNS** the Poll Pad. **ROTATE** the Poll Pad to back to face the Operator, then **PRESS** "Submit".



NOTE: If Voter who needs assistance is visually impaired, a Signature Guide is available for Poll Pad use, found in the Official Table Supply Box. **SLIDE** Poll Pad signature guide on top of the screen to assist with signing.



6. A pop-up will indicate that the Voter's information has been updated. **PRESS** "Accept" to continue processing the Voter.

CONDITIONAL VOTER


If the Voter wants to **change their name**, the Voter is **not found on the Poll Pad**, the Voter **provides a residence address within the state**, or the Voter wants to **register and vote the same day**, the Voter will have to vote **Conditionally**.

CONDITIONAL/PROVISIONAL BALLOT/VOTER REGISTRATION FORM FORMULARIO DE REGISTRO DE VOTANTE/CONDICIONAL/BOLETA PROVISIONAL						Insert Affidavit # here	
TO BE COMPLETED BY ELECTION WORKER - PARA SER COMPLETADO POR EL TRABAJADOR ELECTORAL Instructions for Election Worker: 1.) Print Precinct number above. 2.) Print the Party Ballot Issued (<i>Primary election only</i>). 3.) Issue a ballot with this Provisional/Conditional Envelope 4.) Demonstration Officer: Review envelope, confirm that the voter filled out the "TO BE COMPLETED BY VOTER" section below, including the current residence address and signature .						PRECINCT NUMBER : PARTY BALLOT ISSUED (Primary Election Only) :	
						☐ The voter is a Conditional Voter. (Voter missed the deadline to register to vote or update their voter registration information.)	
VOTED BALLOT ENCLOSED (To Be Opened by Canvassing Board at Elections Office)						BOLETA VOTADA ADJUNTA (Para Ser Abierto por la Junta de Escrutinio en la Oficina Electoral)	
TO BE COMPLETED BY VOTER - IMPORTANT: READ INFORMATION ON OTHER SIDE - PARA SER COMPLETADO POR EL VOTANTE - IMPORTANTE: LEA LA INFORMACIÓN AL REVERSO							
Instructions for Voter: Complete and sign the form below and enclose your ballot into this envelope or your ballot will not be counted. This envelope will also serve as a new voter registration form.				Instrucciones para el Votante: Complete y firme el siguiente formulario e incluya su boleta en este sobre o su boleta no será contada. Este sobre también servirá como un nuevo formulario de registro de votante.			
1	First Name - Primer Nombre	Middle Name - Segundo Nombre	Last Name - Apellido	I am a U.S. citizen and resident of California Soy ciudadano de los EE. UU. y residente de California ☐ YES/SÍ ☐ NO	I am 18 or older Tengo 18 años o más ☐ YES/SÍ ☐ NO	I am 16 or 17 and want to pre-register Tengo 16 o 17 años y quiero pre-registrarme ☐ YES/SÍ ☐ NO	
2	Date of Birth - Fecha de Nacimiento M/Mes / D/Día / YYYY/Año	U.S. state or foreign country of birth - Estado en los EE. UU. o país extranjero donde nació	Driver's License # or Last 4 digits of SSN - Número de su Licencia de Manejar o los últimos 4 dígitos de su Número de Seguro Social or - o		Phone # (optional) - Número de teléfono (opcional) ()		
3	RESIDENCE ADDRESS - DIRECCIÓN RESIDENCIAL	Street Address - Dirección	City - Ciudad	State - Estado	Zip - Código Postal		
4	MAILING ADDRESS (if different from residence address) - DIRECCIÓN POSTAL (si es distinta a la dirección residencial)	Street Address - Dirección	City - Ciudad	State - Estado	Zip - Código Postal		
5	When did you move to the residence address shown above? ¿Cuándo se mudó a la dirección residencial indicada anteriormente? M/Mes / D/Día / YYYY/Año	Previous Residence Address - Dirección Residencial Anterior Street Address - Dirección	City - Ciudad	State - Estado	Zip - Código Postal		
6	VOTE BY MAIL VOTO POR CORREO	All active registered voters will be mailed a vote by mail ballot for every election. If you want to vote in person, you must turn in your vote by mail ballot or you may be required to vote a provisional ballot. A todos los votantes registrados activos se les enviará por correo una boleta de voto por correo para cada elección. Si desea votar en persona, debe entregar su boleta de voto por correo o es posible que se le solicite que vote con una boleta provisional.					
7	PARTY AFFILIATION - AFILIACIÓN DE PARTIDO	☐ American Independent - Americano Independiente ☐ Green - Verde ☐ Peace and Freedom - Paz y Libertad ☐ Democratic - Demócrata ☐ Libertarian - Libertario ☐ Republican - Republicano ☐ Other - Otro _____ ☐ I do not want to choose a political party preference - No quiero elegir una preferencia de partido político ☐ No Party/None - Sin Partida/Ninguno					
8	LANGUAGE PREFERENCE (optional) - PREFERENCIA DE IDIOMA (opcional)	☐ English ☐ Spanish Español ☐ Chinese 中文 ☐ Tagalog ☐ Vietnamese Tiếng Việt					
9	READ, SIGN, AND DATE - LEA, FIRME, Y ESCRIBA LA FECHA	I declare under penalty of perjury that I reside at the address above and have not previously voted in this election either by Vote By Mail or at any other vote center. I declare that I am a resident of California, not currently serving a state or federal prison term for the conviction of a felony and not found mentally incompetent to vote by a court. Declaro bajo pena de perjurio que resido en la dirección anterior y que no he votado previamente en esta elección ni por Voto por Correo ni en ningún otro centro de votación. Declaro que soy residente de California, que actualmente no estoy cumpliendo una pena de prisión estatal o federal por la condena de un delito grave y que un tribunal no me ha declarado mentalmente incompetente para votar.				SIGNATURE - FIRMA ☒ M/Mes / D/Día / YYYY/Año	


- GIVE VOTER** the Conditional Provisional Registration (CPR) Form. **INFORM VOTER** to fill out their information (Sections 1 through 5), select their Party Preference (Section 7), select their preferred language (Section 8) on the Conditional Provisional Registration (CPR) Form, and sign the declaration (Section 9) (**marked blue**).

☒ The voter is a Conditional Voter. (Voter missed the deadline to register to vote or update their voter registration information.)

- MARK** the checkbox indicating that the Voter is a Conditional Voter (**marked orange**).



- Using the Poll Pad and the information on the CPR Form, **PRESS** the "MENU" on the top left corner then **SELECT** "Precinct Finder".



- ENTER** the voter's residential address. Then **PRESS** "NEXT". The Voter's precinct will appear.

1

Insert Affidavit # here

PRECINCT NUMBER :

PARTY BALLOT ISSUED
(Primary Election Only):

LECTORAL

is a Conditional Voter. (Voter missed the deadline to vote or update their voter registration information.)

- On the top-right corner of the CPR Form, **FILL OUT** the "PRECINCT NUMBER" using the information from the Poll Pad.

NOTE: For out of county addresses, **USE** Precinct number "200100". Then proceed to give them a ballot.

YOUTH VOTER IS UNREGISTERED

- The Youth Voter will fill out a Conditional Provisional Registration (CPR) Form.
- CONFIRM** that the Voter answered "NO" to the "I am 18 or older" (Section 1) (**marked blue**). The Date of Birth (Section 2) (**marked orange**) can also be used to further validate.

1	First Name - Primer Nombre	Middle Name - Segundo Nombre	Last Name - Apellido	I am a U.S. citizen and resident of California Soy ciudadano de los EE. UU. y residente de California	I am 18 or older Tengo 18 años o más	I am 16 or 17 and want to pre-register Tengo 16 o 17 años y quiero pre-registrarme
				☐ YES/SI ☐ NO	☐ YES/SI ☐ NO	☐ YES/SI ☐ NO
2	Date of Birth - Fecha de Nacimiento	U.S. state or foreign country of birth - Estado en los EE. UU. o país extranjero donde nació		Driver's License # or Last 4 digits of SSN - Número de su Licencia de Manejar o los últimos 4 dígitos de su Número de Seguro Social		Phone # (optional) - Número de teléfono (opcional)
	M/Mes / D/Día / YYYY/Año			or - o		()

- USE** the Precinct Finder to search for the Youth Voter's precinct.
- FILL OUT** the Precinct Number on the CPR Form, along with the letters "YV" (e.g. "877900 YV") and **MARK** the checkbox indicating that the Youth Voter is a Conditional Voter (i.e. registering and voting on the same day).

CONDITIONAL VOTER

PAPER VOTER

1. **EITHER THE VOTER OR POLL PAD OPERATOR GIVES BOD OPERATOR** the CPR Form to provide the Voter their Ballot. **INFORM VOTER** to proceed to the BOD Operator as their Ballot card(s) print(s).
2. **INFORM VOTER** that their voted Ballot is to be placed in the Envelope before depositing into the Blue Provisional Ballots Trolley.

NOTE: The Conditional Voter should not receive a Secrecy Sleeve

TOUCHSCREEN VOTER


1. **GIVE VOTER** the CPR Form, then **INFORM VOTER** to give the CPR Form to the Demonstration Officer to activate their Ballot on the Ballot Marking Touchscreen by using the information from the CPR Form.
2. **INFORM VOTER** that their printed voted Ballot is to be placed in the Envelope before depositing into the Blue Provisional Ballots Trolley.

NOTE: The Conditional Voter should not receive a Secrecy Sleeve

If the Voter's status on the Poll Pad indicates that the Voter has **already voted**, **inactive Voter status**, **cannot provide ID** when their status says "ID REQUIRED", or the Voter **provides an out of state residence address**, the Voter will have to vote **Provisionally**.

- On the top-right corner of the CPR Form, **FILL OUT** the "PRECINCT NUMBER" using the information from the Poll Pad by searching the Voter's name.

NOTE: For out of state addresses, **USE** Precinct number "200100". Then proceed to give them a ballot.

CONDITIONAL/PROVISIONAL BALLOT/VOTER REGISTRATION FORM FORMULARIO DE REGISTRO DE VOTANTE/CONDICIONAL/BOLETA PROVISIONAL				Insert Affidavit # here		
TO BE COMPLETED BY ELECTION WORKER - PARA SER COMPLETADO POR EL TRABAJADOR ELECTORAL				PRECINCT NUMBER :		
Instructions for Election Worker: 1.) Print Precinct number above. 2.) Print the Party Ballot Issued (Primary election only). 3.) Issue a ballot with this Provisional/Conditional Envelope 4.) Demonstration Officer: Review envelope, confirm that the voter filled out the "TO BE COMPLETED BY VOTER" section below, including the current residence address and signature .				☐ The voter is a Conditional Voter. (Voter missed the deadline to register to vote or update their voter registration information.)		
VOTED BALLOT ENCLOSED (To Be Opened by Canvassing Board at Elections Office)			BOLETA VOTADA ADJUNTA (Para Ser Abierto por la Junta de Escrutinio en la Oficina Electoral)			
TO BE COMPLETED BY VOTER - IMPORTANT: READ INFORMATION ON OTHER SIDE - PARA SER COMPLETADO POR EL VOTANTE - IMPORTANTE: LEA LA INFORMACIÓN AL REVERSO						
Instructions for Voter: Complete and sign the form below and enclose your ballot into this envelope or your ballot will not be counted. This envelope will also serve as a new voter registration form.			Instrucciones para el Votante: Complete y firme el siguiente formulario e incluya su boleta en este sobre o su boleta no será contada. Este sobre también servirá como un nuevo formulario de registro de votante.			
1	First Name - Primer Nombre	Middle Name - Segundo Nombre	Last Name - Apellido	I am a U.S. citizen and resident of California Soy ciudadano de los EE. UU. y residente de California ☐ YES/SI ☐ NO	I am 18 or older Tengo 18 años o más ☐ YES/SI ☐ NO	
2	Date of Birth - Fecha de Nacimiento M/Mes D/Día YYYY/Año	U.S. state or foreign country of birth - Estado en los EE. UU. o país extranjero donde nació	Driver's License # or Last 4 digits of SSN - Número de su Licencia de Manejar o los últimos 4 dígitos de su Número de Seguro Social	Phone # (optional) - Número de teléfono (opcional) ()		
3	RESIDENCE ADDRESS - DIRECCIÓN RESIDENCIAL	Street Address - Dirección	City - Ciudad	State - Estado	Zip - Código Postal	
4	MAILING ADDRESS (if different from residence address) - DIRECCIÓN POSTAL (si es distinta a la dirección residencial)	Street Address - Dirección	City - Ciudad	State - Estado	Zip - Código Postal	
5	When did you move to the residence address shown above? ¿Cuándo se mudó a la dirección residencial indicada anteriormente?	Previous Residence Address - Dirección Residencial Anterior Street Address - Dirección	City - Ciudad	State - Estado	Zip - Código Postal	
6	VOTE BY MAIL VOTO POR CORREO	All active registered voters will be mailed a vote by mail ballot for every election. If you want to vote in person, you must turn in your vote by mail ballot or you may be required to vote a provisional ballot. A todos los votantes registrados activos se les enviará por correo una boleta de voto por correo para cada elección. Si desea votar en persona, debe entregar su boleta de voto por correo o es posible que se le solicite que vote con una boleta provisional.				
7	PARTY AFFILIATION - AFILIACIÓN DE PARTIDO	☐ American Independent - Americano Independiente ☐ Green - Verde ☐ Peace and Freedom - Paz y Libertad ☐ Democratic - Demócrata ☐ Libertarian - Libertario ☐ Republican - Republicano ☐ Other - Otro _____ I do not want to choose a political party preference - No quiero elegir una preferencia de partido político ☐ No Party/None - Sin Partido/Ninguno				
8	LANGUAGE PREFERENCE (optional) - PREFERENCIA DE IDIOMA (opcional)	☐ English ☐ Spanish ☐ Chinese ☐ Tagalog ☐ Vietnamese Español 中文 Tagalog Tiếng Việt				
9	READ, SIGN, AND DATE - LEA, FIRME, Y ESCRIBA LA FECHA	I declare under penalty of perjury that I reside at the address above and have not previously voted in this election either by Vote By Mail or at any other vote center. I declare that I am a resident of California, not currently serving a state or federal prison term for the conviction of a felony and not found mentally incompetent to vote by a court. Declaro bajo pena de perjurio que resido en la dirección anterior y que no he votado previamente en esta elección ni por Voto por Correo ni en ningún otro centro de votación. Declaro que soy residente de California, que actualmente no estoy cumpliendo una pena de prisión estatal o federal por la condena de un delito grave y que un tribunal no me ha declarado mentalmente incompetente para votar.			SIGNATURE - FIRMA  M/Mes D/Día YYYY/Año	

- GIVE VOTER** the Conditional Provisional Registration (CPR) Form. **INFORM VOTER** to fill out their information (Sections 1 through 5), select their Party Preference (Section 7), select their preferred language (Section 8) on the CPR Form, and sign the declaration (Section 9) (**marked blue**).

PROVISIONAL VOTER

PAPER VOTER

1. **EITHER THE VOTER OR POLL PAD OPERATOR GIVES BOD OPERATOR** the CPR Form to provide the Voter their Ballot. **INFORM** the Voter to proceed to the BOD Operator as their Ballot card(s) print(s).
2. **INFORM VOTER** that their voted Ballot is to be placed in the Envelope before depositing into the Blue Provisional Ballots Trolley.

NOTE: The Provisional Voter should not receive a Secrecy Sleeve

TOUCHSCREEN VOTER


1. **GIVE VOTER** the CPR Form, then **INFORM VOTER** to give the CPR Form to the Demonstration Officer to activate their Ballot on the Ballot Marking Touchscreen by using the information from the CPR Form.
2. **INFORM VOTER** that their printed voted Ballot is to be placed in the Envelope before depositing into the Blue Provisional Ballots Trolley.

NOTE: The Provisional Voter should not receive a Secrecy Sleeve


VOTER SUBMITS A VOTER REGISTRATION FORM



1. **PACK** completed Voter Registration Form into the Lime Bag



1. If Election Workers are unable to provide in-person language assistance in the Voter's preferred language, please call one of the hotlines using the Captain (A) Cell Phone. On the cell phone, **SELECT** the green "Phone" icon on the home screen which open the contacts listed on the phone.



2. **SELECT** the tab labeled "Contacts". All available language hotlines, as well as the Election Worker Hotline (labeled "Help Desk Hotline") are located within that tab.

VIDEO CALLING

1. **CALL** the Election Worker Hotline at (510) 835-7205 to notify them to initiate video call.




2. **SELECT** the video camera icon to switch to video either before or after accepting the call.



3. To switch camera (front/back), **SELECT** the icon on the bottom of your screen.

CHARGING POLL PAD


1. **PLUG USB** end of power cable into power cube.
2. **PLUG** power cube into an AC wall outlet.
3. **PLUG** power cable into lightning connector on Poll Pad.
4. **WAIT** about five minutes for the Poll Pad to charge.
5. With sufficient power, Poll Pad will auto power on.
6. **RESUME NORMAL OPERATIONS.**



iOS SOFTWARE UPDATE


DO NOT PERFORM a software update on the Poll Pad. In the unlikely event that an iOS update prompt displays on the device, perform the following steps:


1. From the list of on-screen options, **SELECT** Later.
2. **PRESS** the Home button and verify Poll Pad App remains open.



POLL PAD SCREEN IS UNRESPONSIVE

1. **UNPLUG** unit from power source.
2. **HOLD DOWN** the Sleep/Wake button until the Poll Pad asks to "slide to power off". **POWER OFF** by sliding the on-screen button.
3. **PRESS & RELEASE** the Sleep/Wake button until the Apple logo displays on-screen.
4. After application launches, **RETURN TO PREVIOUS ACTIVITY.**






WIFI & BLUETOOTH CONNECTION

WiFi and Bluetooth connection must stay on at all times.

1. **SWIPE DOWN** from the top-right corner of the screen.
2. **MAKE SURE** the WiFi and Bluetooth is on and highlighted blue.
3. **MAKE SURE** the Brightness and Volume is all the way up.



NOT PRINTING / STOPS PRINTING

1. **MAKE SURE** the printer is turned on.
2. **CONFIRM** the printer is plugged into outlet and cords are securely connected.
3. **VERIFY** paper is installed correctly.
4. **CONFIRM** connection with Poll Pad (green icon).



CHANGING PAPER

1. **OPEN** printer.
2. **RELOAD PAPER** with the paper flap toward you, feeding from the bottom/underneath roll.
3. **CLOSE & PRINT** Test Receipt.

LOST PRINTER CONNECTION



Printer icon will turn red if printer has lost connection to Poll Pad. Press the printer icon, a status box will display, Printer Status: Not Connected.

1. **CLOSE & REOPEN** Poll Pad app, by double clicking the Home button and swiping the app up or by navigating to Exit Application on the MENU screen.

PRINTER BLUETOOTH CONNECTION

If previous troubleshooting steps do not reestablish printer connection, **CHECK** Bluetooth settings.


1. **NAVIGATE** to the Home screen and **SELECT** the Settings app.
2. **SELECT** Bluetooth from the left, **VERIFY** Bluetooth toggle switch is on. **TURN ON** if toggle switch is off.
3. **CHECK** the status of the Star Micronics printer. If Not Connected, **PRESS** on "Star Micronics" to attempt reestablishing bluetooth connection to printer.





PRINTER BLUETOOTH CONNECTION

4. On the back of the printer, **PRESS & HOLD** the "Pair" button for approximately six (6) seconds. The green LED will flash. **RELEASE** the Pair button; the LED will continue to flash green, then change to flashing blue.
5. From the Bluetooth settings, **SELECT** the Star Micronics printer. The light will change to solid blue when connection is successful.
6. In the Bluetooth settings, the Star Micronics printer will now display Connected.
7. **OPEN** the Poll Pad app and **VERIFY** printer icon is green. **COMPLETE** a Test Print to ensure printer is working.




OFFICIAL TABLE BOD OPERATOR


OFFICIAL TABLE BOD OPERATOR



1. **RETRIEVE** Ballot Form from the Poll Pad Operator. **USE** the Ballot Form to retrieve the correct Ballot for the Voter.




3. **CHANGE** the language by clicking the down arrow icon on the Language column to locate the Voter's language preference.




5. A Pop-up window will open indicating the Ballot to be printed. **CLICK** "Print". After printing the Voter's correct Ballot, **SPOIL** Ballot Form by placing Ballot Form in the Purple Spoiled Ballots Bag.

NOTE: Two (2) Election Workers must be present when Ballots are printed. For example, this may be the BOD Operator and the Poll Pad Operator, if they are available.



2. **INPUT** the Precinct number on the Precinct Portion field on the EMS Mobile Ballot Production Application.



4. **SELECT** the Precinct Ballot with the "1of#" (however many cards) Card Name or Card Index "1". Then **CLICK** the on-screen "Print" icon.

NOTE: The on-screen "Print" button must be used at all times. **DO NOT DOUBLE CLICK** when selecting the Ballot to print.

BOD Officer Ballot Cards Index

#	Precinct	Ballot Type	Card Count
1	200100	BTH1	6
2	200200	BTH1	6
3	201400	BTH1	6
4	202000	BTH1	6
5	203000	BTH1	6
6	203000	BTH1	6
7	203000	BTH1	6
8	203000	BTH1	6
9	203000	BTH1	6
10	203000	BTH1	6
11	203000	BTH1	6
12	204010	BTH1	6
13	204010	BTH1	6
14	204010	BTH1	6
15	205000	BTH1	6
16	205000	BTH1	6
17	205000	BTH1	6
18	205000	BTH1	6
19	207000	BTH1	6
20	207000	BTH1	6
21	207000	BTH1	6
22	208010	BTH1	6
23	208010	BTH1	6
24	208010	BTH1	6
25	208010	BTH1	6
26	208010	BTH1	6

6. **USE** the BOD Operator Ballot Cards Index within the BOD Audit Binder to verify the cards/pages printed are the correct amount for the Voter's precinct and Ballot Type.

YOUTH VOTER

Precinct Portion	Ballot Group	Card Name	Card Index	Precinct Portion	Activation Cod	Language	Number Of Prints
 200100YV							
200100YV	Youth Voting	200100YV_BT8YV_Spanish_1	1	0001	200100YV	Spanish	0

If **Voter** is a **Youth Voter**, **SELECT** the Precinct Ballot containing the letters “YV” with the “1of1” Card Name or Card Index “1”. The Ballot Group column can also be filtered to “Youth Voting”. Then **CLICK** the on-screen “Print” icon.

TASK 2 FINISHED BALLOT CARD LOG

TWO (2) PERSON RULE

[illegible]

1. As the Voter's Ballot is being printed, **TURN** to the "Finished Ballot" log within the BOD Audit Binder and **FILL OUT** the **Printer ID** (*as pictured in orange*), the **Vote Center location #**, and the **Election date and Election title** on the top of the page.
2. **WRITE DOWN** the following items in their respective columns:
 - **WRITE DOWN** the **Date/Time**.
 - **WRITE DOWN** the **Ballot On Demand Operator's and second Election Worker's Names**
 - **WRITE DOWN** **Voter's Precinct number**.
 - **WRITE DOWN** **number of Card(s) printed for the Voter**.
3. After the polls have closed, **ADD TOGETHER** number of cards that have been printed that day on the bottom of the page.



“Good morning/afternoon!”



1. **PLACE** Ballot Card(s) in Secrecy Sleeve. **GIVE** to the Voter and **OFFER** a disposable pen.
2. **INFORM VOTER** to keep their Ballot card(s) in the Secrecy Sleeve for their privacy.
3. **OFFER VOTER** assistance by asking: "Do you need assistance with your Ballot?"

IF VOTER SAYS “NO”

INFORM VOTER:

“Thank you. You may proceed to one of the Voting Booths. If you have any questions, please see our Demonstration Officer (**DIRECT VOTER, if necessary**). Voting Instructions are located on the Voting Information Center. After marking your ballot, please see our Demonstration Officer for instructions on depositing your ballots into the Turquoise Bag.”

IF VOTER SAYS “YES”

INFORM VOTER:

“Please see our Demonstration Officer (**DIRECT VOTER, if necessary**). Voting Instructions are located on the Voting Information Center. After marking your ballot, please see our Demonstration Officer for instructions on depositing your ballots into the Turquoise Bag.”

IF THE VOTER IS VOTING CONDITIONAL/PROVISIONALLY:

INFORM VOTER to place Ballot Card(s) in the Conditional Provisional Registration (CPR) Envelope* and sign the CPR Envelope before depositing in the Blue Provisional Ballots Trolley.

** Voters with Conditional Provisional Registration Forms will NOT be given a Secrecy Sleeve and will ONLY be given a pen.*


NOTE: No Ballot printed at the Vote Center can be removed from the Vote Center

VOTER INFORMATION GUIDE ON DEMAND PRINTING


ONLY PRINT VOTER INFORMATION GUIDE IF THE VOTER REQUESTS ONE.



1. **SELECT** the "Voter Information Guides" folder.



2. **SELECT** the Voter's preferred language folder.




3. **DOUBLE CLICK** the Ballot Type. (The Poll Pad or Ballot Form will be required to look-up Voter's information.)



4. **CLICK** the Printer icon to begin printing process.

NOTE: To get the Ballot Type for a Conditional Voter, **USE** the Voter's Precinct Number on the upper right corner of the CPR Form to look up their Ballot Type, either on the BOD Laptop in the 'Card Name' column (e.g. 200100_BT8_Spanish_1of6, where 'BT8' means Ballot Type 8) or the BOD Operator Ballot Cards Index in the BOD Audit Binder.


If Voter is a Youth Voter, the Ballot Type can be obtained similarly, from the BOD Laptop in the 'Card Name' column (e.g. 200100_BT901 - YV_Spanish_1of1, where 'BT901' means Ballot Type 901 and 'YV' means Youth Voting) or the BOD Operator Ballot Cards Index in the BOD Audit Binder.



5. **SELECT** the Printer Destination then **CLICK** "More settings" drop-down menu. **CHANGE** "Scale" options to "Fit to paper". Then **PRESS** "Print".



6. **USE** the paper clip to keep pages together. **GIVE** to the Voter once finished.

ONLY PRINT FACSIMILE REFERENCE BALLOT IF THE VOTER REQUESTS ONE.

1. **SELECT** the "Ballot Facsimiles" folder.



2. **SELECT** the requested language to print, if available.




3. **DOUBLE CLICK** the Ballot Type. (The Poll Pad or Ballot Form will be required to look-up Voter's information.)



4. **CLICK** the Printer icon to begin printing process.

NOTE: To get the Ballot Type for a Conditional Voter, **USE** the Voter's Precinct Number on the upper right corner of the CPR Form to look up their Ballot Type, either on the BOD Laptop in the 'Card Name' column (e.g. 200100_BT8_Spanish_1of6, where 'BT8' means Ballot Type 8) or the BOD Operator Ballot Cards Index in the BOD Audit Binder.

If Voter is a Youth Voter, the Ballot Type can be obtained similarly, from the BOD Laptop in the 'Card Name' column (e.g. 200100_BT901 - YV_Spanish_1of1, where 'BT901' means Ballot Type 901 and 'YV' means Youth Voting) or the BOD Operator Ballot Cards Index in the BOD Audit Binder.



5. **SELECT** the Printer Destination then **CLICK** "More settings" drop-down menu. **CHANGE** "Scale" options to "Fit to paper". Then **PRESS** "Print".



6. **USE** the paper clip to keep pages together. **GIVE** to the Voter once finished.

NOTE: ONLY use Official Vote Center Ballots if both BODs are not operational AND you have offered the use of the Ballot Marking Touchscreens but the Voter insists on a Paper Ballot.

If this occurs, **CONTACT** Election Worker Hotline at (510) 835-7205 for assistance.

PERFORM First Voter Procedures with Teal Unscanned Ballots Bag before first Voter uses this process by showing them that the bag is empty.



Official Vote Center Ballots Index

#	Ballot Type	Language	Card Count	Box Number
Ballot Type: 1				
1	1	Chinese	4	1 of 29
2	1	Spanish	4	1 of 29
3	1	Tagalog	4	1 of 29
4	1	Vietnamese	4	1 of 29
Ballot Type: 2				
5	2	Chinese	4	1 of 29
6	2	Spanish	4	1 of 29
7	2	Tagalog	4	1 of 29
8	2	Vietnamese	4	1 of 29
Ballot Type: 3				
9	3	Chinese	4	1 of 29
10	3	Spanish	4	1 of 29
11	3	Tagalog	4	1 of 29
12	3	Vietnamese	4	1 of 29
Ballot Type: 4				
13	4	Chinese	4	1 of 29
14	4	Spanish	4	1 of 29
15	4	Tagalog	4	1 of 29
16	4	Vietnamese	4	1 of 29
Ballot Type: 5				
17	5	Chinese	4	2 of 29
18	5	Spanish	4	1 of 29
19	5	Tagalog	4	2 of 29
20	5	Vietnamese	4	2 of 29
Ballot Type: 6				

- 1. RETRIEVE** the Ballot Form from the Poll Pad Operator to retrieve the correct Language Ballot and Ballot Type.
- 2. USE** the Official Vote Center Ballot Index (located in the Captain Supply Box) to locate the correct Vote Center Ballots Box based off the Voter's Ballot Type and language.

Vote Center # **1**

ALAMEDA COUNTY
Warehouse - 8000 Capwell Dr ~ Oakland, CA 94621
General Election: 11/5/2024

OFFICIAL VOTE CENTER BALLOTS

BT	Eng/Spa	Eng/Chi	Eng/Tag	Eng/Viet	Total
28	10	10	10	10	40
29	10	10	10	10	40
31	10	10	10	10	40

Box Total Ballot Sets: 600
CARD: A/B/C/D/RCV - 1 SET

PCTCOORD
Proc5

Total Ballot Sets: 420
Box 4 of 14

Official Ballot (BOL/ETA Official)

AVIL 6 DAY

PRECINCT: **1**

- 3.** Within the Official Ballots Delivery Cart, there will be boxes of Official Vote Center Ballots. The label on the front of the box will indicate the Box Number, the Ballot Type(s), and Language Ballot(s) within each box.
- 4.** After retrieving the correct Ballot, **WRITE** the Precinct number down on the bottom-left corner of the Ballot.

NOTE: To get the Ballot Type for a Conditional Voter, **USE** the Voter's Precinct Number on the upper right corner of the CPR Form to look up their Ballot Type, either on the BOD Laptop in the 'Card Name' column (e.g. 200100_BT8_Spanish_1of6, where 'BT8' means Ballot Type 8) or the BOD Operator Ballot Cards Index in the BOD Audit Binder.

If Voter is a Youth Voter, the Ballot Type can be obtained similarly, from the BOD Laptop in the 'Card Name' column (e.g. 200100_BT901 - YV_Spanish_1of1, where 'BT901' means Ballot Type 901 and 'YV' means Youth Voting) or the BOD Operator Ballot Cards Index in the BOD Audit Binder.

5. **TEAR AWAY** the Ballot stub(s) from the top of the Ballot Card(s). **PLACE** Ballot Card(s) in Secrecy Sleeve. **GIVE** the Ballot Card(s) and stub(s) to the Voter, along with Pen.
6. **INFORM VOTER:**
 “Please keep your Ballot Card(s) inside the Secrecy Sleeve. These are your Ballot Card Stub(s). The stub(s) is (are) for you to keep. Once finished, return the Ballot and Secrecy Sleeve to this table. If assistance is needed, please see the Demonstration Officer.”
7. **PLACE** any Voted Official Vote Center Ballot(s) inside the Teal Unscanned Voted Ballots Bag, located underneath the BOD Operator's table, with another Election Worker as a witness.



NOTE: If the Voter is voting Conditionally/Provisionally, **INFORM VOTER** to place Ballot Card(s) in the Conditional Provisional Registration (CPR) Envelope* and sign the CPR Envelope before depositing in the Blue Provisional Ballots Trolley

* Voters with Conditional Provisional Registration Forms will NOT be given a Secrecy Sleeve and will ONLY be given a pen.

OFFICIAL VOTE CENTER BALLOTS RUNNING LOW

- **NOTIFY** Election Worker Hotline at (510) 835-7205.
- **DO THE FOLLOWING ONLY IF OFFICIAL VOTE CENTER BALLOTS RUN OUT PRIOR TO ARRIVAL OF NEW SUPPLIES:**
 1. **SUGGEST** that the Voter use the Ballot Marking Touchscreen.
 2. **If the Voter insists on a Paper Ballot**, the Voter will need to vote on a Sample Ballot, which can be located in the Voter Information Guide.

NOTE: To get the Ballot Type for a Conditional Voter, USE the Voter's Precinct Number on the upper right corner of the Conditional Provisional Registration Form to look up their Ballot Type on the BOD Operator Ballot Cards Index in the BOD Audit Binder.

- A. **IDENTIFY** the Voter's Ballot Type, which can be found on the Poll Pad, and their preferred language.
- B. **REMOVE** the Ballot page in the Sample Ballot; use it as a Ballot for Voter to vote Provisionally.
- C. **ISSUE** Voter a Conditional Provisional Registration Form (*follow Conditional Provisional Voting procedures*).
3. **ENSURE** the Voter fills out the required information and signs the Conditional Provisional Registration Form.
4. When the Voter has finished marking their Ballot,
 - A. **PLACE** the Voted Ballot in the Conditional Provisional Registration Form.
 - B. **SEAL** the Conditional Provisional Registration Form.
 - C. **REMOVE** envelope stub and give it to the Voter.
5. **PLACE** sealed Conditional Provisional Registration Form in the Blue Provisional Ballots Trolley.

NOTE: If BOD Printer runs out of paper, **CONTACT** the Election Worker Hotline (510) 835-7205 for resolutions.

BOD PRINTER PAPER JAM

1. **NOTIFY** Election Worker Hotline at (510) 835-7205. The Hotline will send a replacement.
2. **FILL OUT** the Mobile Ballot Printer Housing Access Log, if necessary.
3. **DO ONE OF THE FOLLOWING ONLY WHEN BOTH BOD PRINTERS ARE NOT OPERATIONAL:**
 - **OFFER** the option to use a **Ballot Marking Touchscreen**;
 - **OFFER VOTER** the option to wait while the replacement BOD Printer is set up;
 - **OFFER** the option of voting at another Vote Center. **INFORM VOTER** to visit acvote.alamedacountyca.gov/GO for locations;
 - Or **OFFER** the option of voting at **the Registrar of Voters' Office, 1225 Fallon Street, Room G-1, Oakland, CA 94612** (Public entrance on 12th Street).

SPOILING PAPER BALLOT



1. **RETRIEVE** Printed Voted Ballot from Voter, then **WRITE "SPOILED"** on the Ballot. **USE** the Spoiled Ballot as a reference for printing a new Ballot.

NOTE: The Voter can decide to change their Voting method.



2. **PLACE** the Spoiled Ballot into **Purple Spoiled Ballots Bag**.

SPOILING PAPER BALLOT

3. **REPRINT** a new set of Ballot card(s) using the Precinct and Ballot Type from the Spoiled Ballot Card(s).
4. **ONLY GIVE VOTER** the requested Ballot card(s), **NOT** the whole set unless specified. **WRITE DOWN** the number of Ballot card(s) printed for the Voter on the Finished Ballot Card Log.
5. **INFORM VOTER:**
 “Under State Law, a Voter shall not receive more than a total of three (3) Ballots, including the original Ballot.”
6. **OFFER VOTER** assistance with their Ballot.
7. **WRITE** “SPOILED” on remaining new Ballot card(s) and place into **Purple Spoiled Ballots Bag**. **WRITE DOWN** the letters and number of remaining new Ballot card(s) on the Damaged Ballots Inventory Control Log.

FOR EXAMPLE, if Voter requests a NEW D-letter Ballot Card:

1. **RETRIEVE** D-letter Ballot card from Voter, write “SPOILED” on card and place into Purple Spoiled Ballots Bag.
2. **PRINT** a new set of Ballots.
3. **REMOVE** new D-letter Ballot card from set and **GIVE** to the Voter. **WRITE DOWN** 1 Ballot Card printed on the Finished Ballot Card Log.
4. **WRITE “VOID”** remaining cards of the new set and **PLACE** into Purple Spoiled Ballots Bag. **WRITE DOWN** the letters (A, B, C) and number (3) of the remaining cards on the Damaged Ballot Inventory Control Log.

SPOILING TOUCHSCREEN BALLOT

1. **RETRIEVE** Printed Voted Ballot from Voter, **RECORD** Precinct number for new Ballot Marking Touchscreen activation, then **WRITE** “SPOILED” on the Ballot.
2. **PLACE** into Purple Spoiled Ballots Bag.
3. **INFORM VOTER:**
 “Under State Law, a Voter shall not receive more than a total of three (3) Ballots, including the original Ballot.”
4. **OFFER VOTER** assistance with their Ballot.
5. **REACTIVATE** the Voting session on Ballot Marking Touchscreen.



NOTE: The Voter can decide to change their Voting method.

- 1. In an event of a Ballot card being misprinted, damaged, or jammed during the printing process, WRITE "Void" on each of the Ballot card(s) in the set.**

NOTE: For Spoiled printed Ballots, WRITE
“SPOILED” on the card(s) that need to be
 replaced and **“VOID”** the extra reprinted
 card(s) the Voter may not need.

2. **REPRINT** a new set of Ballot Cards for the Voter and **WRITE DOWN** the number of card(s) on the Finished Ballot Card Log. Then, **TURN** to the "Damage Ballot Inventory Control Log" in the BOD Audit Binder.
3. **FILL OUT** the **Printer ID**, the **Vote Center location #**, and the **Election date and Election title** on the top of the page.
4. **COMPLETE** the following information on the "Damaged Ballots Inventory Control Log":
 - Date/Time.
 - Ballot On Demand Operator's and second Election Worker's Names.
 - Precinct number, letter of Card(s), number of Card(s) damaged.
5. **PLACE** the entire set of Ballot Cards, including the misprinted, damaged, or jammed Ballots Cards into Purple Spoiled Ballots Bag.
6. At the end of the day, **COUNT** number of cards that have been entered on each page of the log.
7. Date Destroyed and Initials are left BLANK.

[illegible]

1. In an event of a **BOD Printer malfunction**, **CONTACT** the Election Worker Hotline at (510) 835-7205.

2. In the BOD Audit Binder, **TURN** to the "Democracy Suite Mobile Ballot Printer Housing Access Log".

3. **FILL OUT** the **Vote Center location #** and the **Election date and Election title** on the top of the page.

4. **WRITE DOWN** the following items in their respective columns:

- Date/Time.
- Ballot On Demand Operator's and second Election Worker's or Troubleshooter's names.
- "ROV" under the "Company/Agency/Department" column.
- Reason Code with the assistance of the column to the right of it.
- **If troubleshooting requires breaking the seal to open the Printer, WRITE DOWN** the current Red Seal number and the replacement Red Seal number under their respective columns. **PLACE** the removed Red Seal(s) on the Seal Verification Form.

11/8/22 General Election
(Date/Name of Election)

PRINTER ID: 12

VOTE CENTER #: 4 Democracy Suite Mobile Ballot Printer Housing Access Log

Date/Time	Employee 1 Name (Print)	Employee 2 Name (Print)	Company/Agency/Department	Reason Code	Access Reason Codes	Old Security Seal #	New Security Seal #
11/8/22 12:01p	Angel Padilla	Noe Lucio	ROV	3	1. Unfinished Ballot Card Loading 2. Unfinished Ballot Card Unloading 3. Paper Jam 4. Toner 5. Maintenance (Service Call, Repair, Inspection)	223344	556677

Exhibit E

BALLOT PRINTING SYSTEM BALLOT IMAGES DELETION LOG

TWO (2) PERSON RULE

1. In an event of a file or Ballot being deleted from the provided **BOD Laptop by an Election Worker**, **CONTACT** the Election Worker Hotline at (510) 835-7205.

2. In the BOD Audit Binder, **TURN** to the "Democracy Suite Ballot Printing System Ballot Images Deletion Log".

3. **FILL OUT** the **Vote Center location #** and the **Election date and Election title** on the top of the page.

4. **WRITE DOWN** the following items in their respective columns:

- Date/Time.
- Ballot On Demand Operator's and second Election Worker's names.
- "ROV" under the "Company/Agency/Department" column.
- Election date in the "Election Date" column.
- Number of files deleted.

11/8/22 General Election
(Date/Name of Election)

VOTE CENTER #: 12

Democracy Suite Ballot Printing System Ballot Images Deletion Log
(Log to be Transmitted to Secretary of State's Office)

Date/Time	Employee 1 Name (Print)	Employee 2 Name (Print)	Company/Agency/Department	Election Date	Total Number of Files Deleted
11/8/22 12:01p	Angel Padilla	Noe Lucio	ROV	11/8/22	1

Exhibit F

OFFICIAL TABLE DEMONSTRATION OFFICER

OFFICIAL TABLE DEMONSTRATION OFFICER



“Good morning/afternoon!

How may I assist you?”

Instructions on how to mark the Ballot are posted on the Voter Information Center (**DIRECT VOTER if necessary**) and translated in all supported languages.

1. **FOLLOW** Ballot Activation instructions in the *Touchscreen Operating Instructions* located in the Operations Sleeve on the side of the Voting Booth and the Election Worker Guide (pg. 145).
2. **COLLECT** the Ballot Form from the Voter, and **GIVE** the Ballot Form to the BOD Operator. (The BOD Operator will SPOIL Ballot Form by placing it in the Purple Spoiled Ballots Bag.)



NOTE: DO NOT ASK ABOUT OR MENTION A VOTER'S DISABILITY. Etiquette Guidelines regarding *Disability Sensitivity at the Polls* are available in the Election Worker Guide.

TASK 2 DEPOSITING BALLOT

- **MONITOR** that Voters are depositing in the correct Trolleys, as follows:

TURQUOISE OFFICIAL BALLOTS BAG

FOR VOTED PRINTED PAPER
AND TOUCHSCREEN BALLOTS



1. From the Secrecy Sleeve, **VOTER DEPOSITS** all Ballots into Turquoise Official Ballots Bag.




NOTE: The piece of paper (similar to the image on left) printed by the Ballot Marking Touchscreen is an **OFFICIAL BALLOT** and **must be placed in the Turquoise Official Ballots Bag** in order for the ballot to be counted.

TASK 2 DEPOSITING BALLOT

BLUE PROVISIONAL BALLOTS TROLLEY

FOR ALL CONDITIONAL/PROVISIONAL
BALLOTS ONLY

PAPER VOTER



VOTED BALLOT
CARD(S)

CONDITIONAL
PROVISIONAL
REGISTRATION (CPR) FORM

TOUCHSCREEN VOTER



PRINTED VOTED
BALLOT

CONDITIONAL
PROVISIONAL
REGISTRATION (CPR) FORM



1. **DETACH** CPR Form stub and **GIVE** the stub to the Voter.
2. **CHECK THE FOLLOWING:**
 - **Ballot is inside** the CPR Form.
 - CPR Form is **filled out, signed, and sealed**.



3. **DEPOSIT** CPR Form into Blue Provisional Ballots Trolley.
- INFORM VOTER:**
“To find out the status of your ballot, please visit the ‘My Voter Profile’ page on the ROV website at acvote.alamedacountyca.gov/mvp or call (510) 272-6973 (Toll Free (800) 834-6454) at least 30 days after the election.”

NOTE: DO NOT ALLOW BALLOTS IN SECRECY SLEEVES to be deposited in the Blue Provisional Ballots Trolley. **REDIRECT VOTER** to the Turquoise Official Ballots Bag and **FOLLOW** the corresponding instructions for depositing the Ballot.

YELLOW VOTE BY MAIL BALLOTS TROLLEY

FOR VOTE BY MAIL BALLOTS WITH ENVELOPES



1. **VERIFY** VBM Envelope is signed and sealed.
2. **DEPOSIT** into Yellow Vote by Mail Ballots Trolley.

REPLACEMENT VBM ENVELOPE

1. **VERIFY** that the Voter has filled out the back of the envelope completely.
2. **VERIFY** VBM Envelope is **signed and sealed**.
3. **DEPOSIT** into Yellow Vote by Mail Ballots Trolley

The VBM Replacement envelope is for a complete set of Ballot Card(s).



VBM VOTER SCENARIOS

IF A VBM VOTER SUBMITS AN RAVBM (REMOTE ACCESS VOTE BY MAIL) BALLOT:

- **INFORM VOTER** to double check that they have their printed Ballot and the required documents containing their signature. They can submit into the Yellow Trolley with their provided envelope or a replacement envelope.
- **If the Voter needs a replacement envelope for their RAVBM Ballot**, the Voter can use a replacement VBM Envelope.

TASK 3 VOTERS EXITING

1. **DISTRIBUTE** "I Voted" Stickers as Voters are on their way out of the Vote Center.

ASSISTANCE MARKING THE BALLOT

Instructions on how to mark the Ballot are posted on the Voter Information Center and translated in all supported languages. **FOLLOW** Ballot Activation instructions in the Ballot Marking Touchscreen Operating Instructions located in the Operations Sleeve and the Election Worker Guide.

By law, a Voter may be assisted by up to two (2) persons in marking their Ballot. If a Voter requires assistance from an Election Worker or anyone else (with the exception of the Voter's employer or union agent), Help the Voter as needed.

NOTE: DO NOT ASK about or mention a Voter's disability. Etiquette Guidelines regarding *Disability Sensitivity at the Polls* are available in the Election Worker Guide.

VOTER LEAVES BEFORE CASTING BALLOT

FOR PAPER BALLOT:

1. Two (2) Election Workers deposit the Ballot AS IS in the Turquoise Official Ballots Bag.

FOR TOUCHSCREEN PRINTED VOTED BALLOT:

1. Two (2) Election Workers must go to the Ballot Marking Touchscreen.
2. One (1) Election Worker advances the Ballot to the Review Screen and selects the "Print Ballot" option while the other acts as a witness.
3. Two (2) Election Workers deposit the Ballot in the Turquoise Official Ballots Bag.

FOR VOTE BY MAIL BALLOT:

Two (2) Election Workers enclose the Ballot AS IS in a Vote by Mail Ballot Envelope and deposit into the Yellow Vote by Mail Ballots Trolley.

BALLOT MARKING TOUCHSCREEN PAPER REFILL

1. To ensure the Printer Paper does not run out during a Voting Session, **CHECK** "Total ballots printed" on the bottom left-hand corner of the Ballot Marking Touchscreen.
2. Once "Total ballots printed" reaches 100, **CONTACT** the Election Worker Hotline at (510) 835-7205.

VOTERS WITH DISABILITIES

VOTERS WITH DISABILITIES

CALIFORNIA SECRETARY OF STATE

The rules of etiquette and good manners apply when working with every Voter who enters a Vote Center. In addition, the following guidance may be helpful when working with Voters with disabilities.

MEETING A VOTER WITH A DISABILITY

- **Greet everyone with a smile, eye contact, and a spoken greeting.** Some people are uncomfortable with handshaking or physical contact. Be respectful of personal boundaries.
- **Speak directly to a Voter with a disability,** not just to others accompanying a Voter.
- **Offer assistance, but do not insist on providing it.** It is best to ask all Voters if they need assistance or would like to use an accessible voting system, instead of assuming who may or may not have a disability. Always ask how you may best assist before acting, wait until the offer is accepted, and then listen or ask for instructions. For example, it is rude and may be unsafe to grab a walker, white cane, or other aid used by a Voter who is disabled.
- **Don't ask about or mention a Voter's disability** unless they talk about it or it is relevant to the conversation. Don't praise someone with a disability for having "overcome" the disability. All Voters are equal. Don't patronize or talk down to someone with a disability.
- **Keep your communications simple.** Keep sentences short and rephrase or repeat your comments if the Voter is not understanding you. Focus on one topic at a time and be sure to allow time for the Voter to respond. Also, pay attention to the Voter while you're speaking with them, as they may be using body language to communicate.

MEETING SOMEONE WHO HAS A VISUAL IMPAIRMENT

- **Greetings.** Identify yourself and introduce anyone else who may be with you. Also, don't leave the Voter without saying you are leaving.
- **Guiding.** If asked to be a human guide, place your arm against their hand or close enough that they can easily find it. Never push or pull someone, always point out obstacles along the way, and discuss where you are going.
- **Guide and service animals.** Do not pet or distract a guide or service animal. People with visual impairments often use guide or service animals. However, be aware that people with other disabilities may use guide or service animals as well. Guide and service animals are well trained and friendly, not to be feared.

INTERACTING WITH A VOTER WHO USES A MOBILITY DEVICE (E.G., WHEELCHAIR, SCOOTER, CANE, ETC.)

- **Provide personal space.** Do not push, lean on, or hold onto a Voter's mobility device unless the Voter asks. Remember, the mobility device is part of their personal space.
- **Clear the path.** Make sure that the path of travel to the check-in tables and voting booths are clear before the polls open and remains clear throughout the day.
- **When giving direction to someone using a mobility device,** consider the distance, weather, and physical obstacles such as curbs and stairs that the Voter will encounter. Know where the accessible pathways, restrooms, and water fountains are both in and outside of the building.

COMMUNICATING WITH SOMEONE WHO IS DEAF OR USES AN ASSISTIVE HEARING DEVICE

- **Let the Voter take the lead** in establishing which communication method he or she prefers to use (e.g., assistive technology, writing on a piece of paper).
- **Talk directly to the Voter** even if a sign language interpreter is present. For some people, it also may help to simplify sentences and use more body expressions.

DISABILITY SENSITIVITY

MEETING SOMEONE WITH A DISABILITY THAT AFFECTS SPEECH

- **Pay attention, be patient, and wait** for the person to complete a thought and do not try to finish it for them. Ask the person to repeat the thought if you do not understand what they are trying to say.
- **Understand a person may use assistive technology** such as an alphabet board or computer to communicate.

USE APPROPRIATE LANGUAGE

- Instead of disabled Voter, **say Voter with a disability.**

There are two federally mandated Acts that require the voting process be fully accessible to Voters with disabilities and/or Voters with special needs:


- Americans with Disabilities Act (ADA)
- Help America Vote Act (HAVA)

Information derived from the California Secretary of State (as of January 25, 2016)
Available at: <http://www.sos.ca.gov/elections/voting-resources/voters-disabilities>

Election Workers should check outside frequently for Curbside Voters. If a Curbside Voting appointment has been made in advance, the Captain of the Vote Center will be notified about these appointments. After greeting the Curbside Voter, the Election Worker will return to the Vote Center to retrieve any necessary materials, and another Election Worker. Ensure at least two (2) Election Workers accompany all voting materials. **ONLY** a Paper Ballot can be provided to a Curbside Voter.

FOLLOW THE PROCEDURES BELOW:

- Two (2) Election Workers, with a Poll Pad, stylus, and a Poll Pad signature guide, will be sent out to the Curbside Voter for processing. **TAKE** an Election Worker Guide for reference. **FOLLOW** the Poll Pad Operator procedures for checking in a Voter. **MARK** the Voting Method as “Paper” and the Voter as “Curbside Voter” on the Poll Pad before completing the process.
 - ASK VOTER** if they need any assistance in completing a Paper Ballot, including any supplies (magnifier, pen with grip, etc.).
 - If Curbside Voter’s information is not on the Poll Pad, FOLLOW** the Conditional Provisional Voting Form instructions, procedures, and options.
- RETURN** Poll Pad and other voting materials to Official Table and **PRINT** a Paper Ballot for Voter.
- Two (2) Election Workers will **TAKE** the Paper Ballot (inside a Secrecy Sleeve), a Pen, and an “I Voted” sticker to the Voter. Include any requested assistive supplies if applicable (magnifier, pen with grip, etc.)
- After Voter privately completes Ballot, **ASK VOTER** to place Ballot back into Secrecy Sleeve; **RETRIEVE** Secrecy Sleeve with Ballot inside.
- INFORM VOTER** that the voting process is completed and **GIVE** “I Voted” sticker.
- RETURN** to the Vote Center and **DEPOSIT** the Voted Ballot into Turquoise Official Ballots Bag. Take “I Voted” sticker for the Voter.
 - If Curbside Voter is using the Conditional Provisional Voting Envelope, DEPOSIT** the envelope into Blue Provisional Ballots Trolley.



NOTE: A Vote by Mail (VBM) or In-Person VBM may be assisted as a Curbside Voter. Two (2) Election Workers must be present while retrieving the VBM Ballot.

SUPPLIES FOR VOTERS WITH DISABILITIES



**ACCESSIBLE ENTRANCE
A-FRAME**



CURBSIDE A-FRAME



ACCESSIBLE VOTING BOOTH



- LIGHT
- MAT
- RAMP



- MAGNIFIER
- PEN WITH GRIP
- SIGNATURE GUIDE



**BALLOT MARKING
TOUCHSCREEN**



**AUDIO TACTILE INTERFACE
(ATI)**



**BALLOT MARKING
TOUCHSCREEN
TRANSCRIPT**



POLL PAD SIGNATURE GUIDE

BALLOT MARKING TOUCHSCREEN: VOTING

BALLOT MARKING TOUCHSCREEN: VOTING



1. **RETRIEVE** Ballot Form from Voter.



2. **INSERT** Poll Worker Card in the Card Reader Slot. Keep Card inserted.



3. **USE** the Ballot Form (CPR Form, if applicable) to enter the Voter's correct precinct. **PRESS** "Activate" to continue after the Precinct has been entered.

NOTE: When activating the Ballot Marking Touchscreen for a Youth Voting precinct, **ADD "Y"** to the end of the precinct number.

4. **SPOIL** Ballot Form by placing it into the Purple Spoiled Ballots Bag.




5. **REMOVE** Poll Worker Card.



6. **VOTER SELECTS** preferred language to continue.



1. After entering the Voter's precinct, **SELECT** "Enable AVS Controller" checkbox to enable an Accessible Voting Session. **PRESS** "Activate" to continue.
2. **REMOVE** Poll Worker Card.
3. **VOTER SELECTS** preferred language to continue.



4. **ASK VOTER:**
"What is your preferred mode of accessible voting?"

NOTE: If Voter choose the ATI, the Voter can then select "Yes" or "No" to activate the Privacy Mask during the Accessible Voting Session.



5. **INFORM VOTER** about the following options:
 - Located on the upper right-hand corner of the screen, **Language** and **Text Size** can be adjusted to the Voter's preference.
 - **"View"** button will provide some options for Ballot viewing preference.
 - **"More"** button will provide the following options:
 1. Quit voting.
 2. Proceed to the next Contest, **if the Privacy Mask is on.**
 3. Review your Ballot choices.
6. **OFFER VOTER** the use of a chair.

AUDIO TACTILE INTERFACE (ATI)


1. INFORM VOTER:

“This will provide audio guidance allowing you to navigate and make selections.”

2. SELECT “ATI” option on the screen.

3. Voter should be comfortably positioned with ATI and headphones.

NOTE: Assist Voter with Voting Process if requested.




CANCELING ACTIVATION

If the Voter would like to cancel the voting session:

1. SELECT “More” on the top right of the screen.

2. SELECT “Quit voting.”

3. SELECT “Yes, quit voting” on the pop-up selection window.



USB CHANGE IS DETECTED

1. **MAKE SURE** the Ballot Marking Touchscreen Printer cable is plugged into the Printer.
2. **MAKE SURE** the cable on top of the ATI is plugged in securely.
3. **INSERT** Poll Worker Card into the Ballot Marking Touchscreen, then enter Administration Login number.
4. **PERFORM** Hardware Test on both the ATI and Printer. *(Follow Steps 4-10, on pgs. 80-82)*
5. **REMOVE & RE-INSERT** Poll Worker Card to re-activate Voting Session.*
**This will require Voter to start from the beginning of the session.*
6. **If the problem(s) persist, CONTACT** the Registrar of Voters' Election Worker Hotline for further assistance.

ATI HAS NO AUDIO

1. **MAKE SURE** the headphones are plugged into the correct port and plugged in completely.
2. **MAKE SURE** the cable on top of the ATI is plugged in securely.
3. **ACTIVATE** new Accessible Voting Session ensuring that "Enable AVS Controller" check-box is selected when activating.
4. **If the problem(s) persist, CONTACT** the Registrar of Voters' Election Worker Hotline for further assistance.

BALLOT MARKING TOUCHSCREEN NOT FUNCTIONAL

1. **DIRECT** the Voter to use an available Ballot Marking Touchscreen.
2. **If Voter does not wish to use another available Ballot Marking Touchscreen, or all Ballot Marking Touchscreens are not functional, GIVE VOTER** the three (3) following options on how to proceed:
 - **OFFER** a Paper Ballot and **OFFER** assistance.
 - **OFFER** the option of voting on a Ballot Marking Touchscreen at another Vote Center
 – **CONTACT** Election Worker Hotline (510) 835-7205 to get information for closest available Vote Centers.
 - **OFFER** the option of voting on a Ballot Marking Touchscreen located at **the Registrar of Voters' Office, 1225 Fallon Street, Room G-1, Oakland, CA 94612** (public entrance on 12th Street).
 - *The Voter may call Registrar of Voters (510) 272-6933 with any questions and concerns.*
3. **CONTACT** the Election Worker Hotline (510) 835-7205 with regard to the Ballot Marking Touchscreens that are not functioning.

ELECTION SCENARIOS

ELECTION SCENARIOS

ELECTIONEERING

Electioneering within 100 feet of the Vote Center is prohibited (CEC § 18370). Violations can lead to fines and/or imprisonment.

Within the immediate vicinity of a person in line to cast their ballot or within 100 feet of the entrance of a voting location, curbside voting, or drop box the following activities are prohibited:

- **DO NOT** ask a person to vote for or against any candidate or ballot measure.
- **DO NOT** display a candidate's name, likeness, or logo.
- **DO NOT** display a ballot measure's number, title, subject, or logo.
- **DO NOT** display or distribute buttons, hats, pencils, pens, shirts, signs, or stickers containing electioneering information.
- **DO NOT** disseminate audible electioneering information.
- **DO NOT** obstruct access to, loiter near, or disseminate visible or audible electioneering information at vote-by-mail ballot drop boxes.
- **DO NOT** circulate any petitions, including initiatives, referenda, recall, or candidate nominations.
- **DO NOT** display information or speak to a Voter about the Voter's eligibility to vote.

If you encounter electioneering, call the Election Worker Hotline at (510) 835-7205.

NO ELECTIONEERING IS PERMITTED

WITHIN 100 FEET OF A VOTE CENTER OR CURBSIDE VOTING AREA

YOU ARE APPROXIMATELY 100 FEET FROM VOTE CENTER OR CURBSIDE VOTING AREA

NO SE PERMITE CAMPAÑA ELECTORAL A MENOS DE 100 PIES DEL CENTRO DE VOTACIÓN O DEL ÁREA DE VOTACIÓN EN LA ACERA

USO SE ENCONTRARÁ APROXIMADAMENTE A 100 PIES DEL CENTRO DE VOTACIÓN O DEL ÁREA DE VOTACIÓN EN LA ACERA

투표 센터 또는 도표면 부류 구역에서 100 피트 이내에서는 선거 운동 활동이 허용되지 않습니다

투표 센터 또는 도표면 부류 구역으로부터 약 100 피트 떨어진 곳에서

உள்ளேயுள்ளவருக்கிடையேயுள்ளவருக்கிடையே தலை 100 பீடில் இருந்து விலகியுள்ளதில் உள்ள இடங்களில் வாக்குப்பதிவு

ආවේණිකව පවතින ස්ථානවල සිට 100 පීඩ් දුරින් සිටින ස්ථානවල

உள்ளேயுள்ளவருக்கிடையேயுள்ளவருக்கிடையே தலை 100 பீடில் இருந்து விலகியுள்ளதில் உள்ள இடங்களில் வாக்குப்பதிவு

在距離投票中心或道路投票區 100 英尺範圍內不得進行競選活動

您距離投票中心或道路投票區約 100 英尺

இருள்வாழ்வுபெற்றவர்களுக்கிடையேயுள்ளவருக்கிடையே தலை 100 பீடில் இருந்து விலகியுள்ளதில் உள்ள இடங்களில் வாக்குப்பதிவு

ආවේණිකව පවතින ස්ථානවල සිට 100 පීඩ් දුරින් සිටින ස්ථානවල

TULZI JANGSUNG MAN NGANG 100 NING HA
DANGKJ KUNGJONG HO MOHO KUNGJONG
NANG NANGZANG NGANGS 100 NING HA
DANGKJ KUNGJONG HO MOHO KUNGJONG

WALANG IPNANHINTULUT NA
PANGANGAMPAYNA SA LOOB NG 100
TALAMPARAN NA SA SENTRO NG PAGBAYO
O SA LUGAR NG PAGBAYO SA GILID NG PASADAN
KAWAY NA NANGA HUMAGT KUMALANG 100
TALAMPARAN NA SA SENTRO NG PAGBAYO
O SA LUGAR NG PAGBAYO SA GILID NG PASADAN

ඔබේ වෙළඳාම හෝ වෙනත් කටයුතු වෙළඳාම 100 පීඩ් ට වඩා ඊට වෙනම වෙළඳාම හෝ වෙනත් කටයුතු

ඔබේ වෙළඳාම හෝ වෙනත් කටයුතු වෙළඳාම 100 පීඩ් ට වඩා ඊට වෙනම වෙළඳාම හෝ වෙනත් කටයුතු

සමාජානුකූලව සම්බන්ධ කරගන්නා ස්ථානවල සිට 100 පීඩ් දුරින් සිටින ස්ථානවල

සමාජානුකූලව සම්බන්ධ කරගන්නා ස්ථානවල සිට 100 පීඩ් දුරින් සිටින ස්ථානවල

KHÔNG ĐƯỢC PHÁP VẬN ĐỘNG SỰ CỬ TRỌNG TRONG 100 FEET TRƯNG TÂM BỐ PHƯƠNG HOẶC KHU VỰC BỐ PHƯƠNG BÊN LỀ

QUY VỊ X KHOẢNG 100 FEET TRƯNG TÂM BỐ PHƯƠNG HOẶC KHU VỰC BỐ PHƯƠNG BÊN LỀ

සමාජානුකූලව සම්බන්ධ කරගන්නා ස්ථානවල සිට 100 පීඩ් ට වඩා ඊට වෙනම වෙළඳාම හෝ වෙනත් කටයුතු

ඔබේ වෙළඳාම හෝ වෙනත් කටයුතු වෙළඳාම 100 පීඩ් ට වඩා ඊට වෙනම වෙළඳාම හෝ වෙනත් කටයුතු

CAHALI 0808 T88 30CB3I CAHALI 0808 T808M1 T8080C 100 0001 2010P
CONE YOUNG KONGMANT 0808 10000100
X08100100

TA CAHALI 0808 T88 30CB3I CAHALI 0808 T808M1 T8080C 100 0001 2010P
CONE YOUNG KONGMANT 0808 10000100
X08100100

ALAMEDA COUNTY
Registrar of Voters

VOTER INTIMIDATION

Voter intimidation is illegal and is a serious offense. It is a felony if any person “makes use of or threatens to make use of any force, violence, or tactic of coercion or intimidation” to induce or compel any other person to vote or refrain from voting, refrain from voting for any particular person or measure at any election; or because any person voted or refrained from voting at any election or voted or refrained from voting for any particular person or measure. It is also a felony if anyone hires or arranges for any other person to do any of the above. (Elec. Code, § 18540.)

While such acts of voter intimidation may happen in and around a Vote Center (immediate vicinity), they may occur anywhere. Such acts may include, for example:

- Blocking access to voting locations
- Threatening criminal action against voters
- Presenting false information about voter eligibility requirements, including criminal consequences for voting (e.g., credit card debt, arrest warrant checks, etc.)
- Harassing or threatening behavior, including aggressive questioning of voters based on a person's race, gender identity, or aggressively questioning voters about their citizenship, criminal record, or other qualifications to vote
- Challenging voters' right to vote
- Presenting false information to voters about the voting process and requirements, including the ability to speak English, or the need to present certain types of photo identification
- Assault, battery, threats of violence, brandishing of weapons

If you encounter voter intimidation, call the Election Worker Hotline at (510) 835-7205.

MEDIA AT THE VOTE CENTER

Voting is, by necessity and design, a public process. As the purveyors of information to the public, members of the various media may arrive at the Vote Center to cover one or more aspects of the process for their viewers, readers, or listening audience. **The media MAY NOT INTERFERE with the voting process in any way.** Listed below are general guidelines for members of the media.

CAN DO:

- Complete exit polls at least twenty-five (25) feet from all entrances to the Vote Center.
- With the permission of the Registrar of Voters, a credentialed media organization may photograph or film a candidate voting at a Vote Center, as long as such activity does not interfere with voting, is not intimidating to any voters or election workers, and that the privacy of voters is not compromised.

CANNOT DO:

- Interfere with the Voting Process or touch voting equipment.
- Photograph, video, or otherwise record a Voter entering or exiting the Vote Center without permission.
- Block entrances, exits, curbside voting, parking or accessible paths.

MUST DO:

- Photographers or videographers must get permission from subjects and must ensure that neither a Voter's Paper Ballot nor on-screen Touchscreen Ballot are legible in the photo or video footage.

Election Workers are limited to comment on those issues about which they have first-hand knowledge.

Technical questions or questions regarding policies or procedures should be directed to the Alameda County Registrar of Voters (510) 272-6933.

If you encounter any media present at the Vote Center, call the Election Worker Hotline at (510) 835-7205.

CAMERAS AT THE VOTE CENTER

California Elections Code section 14291 allows a voter to “voluntarily disclose how he or she voted if that voluntary act does not violate any other law.”

A Voter may now take a photograph of their Ballot (a “Ballot Selfie”) and share it on social media. While “Ballot Selfies” are allowed under California law, Election Workers will still need to exercise their discretion as to whether “Ballot Selfies” cause disruptions requiring a response.

Overall, voters must be mindful that their ability to take “ballot selfies” is not without limits. The voting process must be private and free from any form of intimidation or coercion.

DE-ESCALATION

De-Escalation is a method to prevent potential violence. Individuals are encouraged to use purposeful actions, verbal communications, and body language to calm a potentially dangerous situation. Your safety and the safety of others is the highest priority. Maintain a safe distance and avoid being alone with an individual who is combative or potentially violent. If there is a risk of imminent violence, remove yourself from the situation and seek safety.

KNOW YOUR LIMITS

Keep in mind that some individuals may be more adept in applying these techniques. Know your own vulnerabilities and tendencies and recognize that sometimes the best intervention is knowing when to seek additional help.

OBTAIN HELP

If you feel the individual or situation is escalating and violence may occur, call for help from your security staff or local law enforcement and move yourself to a safe location.

TIPS

Be aware of your non-verbal communications. Ensure your tone, facial expressions, body language, and gestures relay calm and empathy. Remain respectful and courteous. Address the individual with civility and use phrases such as “please” and “thank you.”

PURPOSEFUL ACTIONS

- **Remain Calm:** A purposeful demonstration of calmness and composure can enable de-escalation.
- **Change the Setting:** If possible, remove people from the area. This could involve parties to the conflict and onlookers.
- **Respect Personal Space:** Maintain a safe distance and avoid touching the other person.
- **Listen:** Give your full attention, nod, ask questions, and avoid changing the subject or interrupting.
- **Empathize:** Present genuine concern and a willingness to understand without judging.

VERBAL COMMUNICATION

Tone + Volume + Rate of speech + Inflection of voice = Verbal De-Escalation

- **Tone:** Speak calmly to demonstrate empathy.
- **Volume:** Monitor your volume and avoid raising your voice.
- **Rate of Speech:** Slower can be more soothing.
- **Inflection:** Be aware of emphasizing words or syllables as that can negatively affect the situation.

Instead Of:	Say...
“Calm down.”	“I can see that you are upset...”
“I can’t help you.”	“I want to help, what can I do?”
“I know how you feel.”	“I understand that you feel...”
“Come with me.”	“May I speak with you?”

BODY LANGUAGE

Instead Of:	Try...
Standing rigidly in front of the person	Keeping a relaxed and alert stance off to the side of the person
Pointing your finger	Keeping your hands down, open, and visible at all times
Excessive gesturing or pacing	Using slow, deliberate movements
Faking a smile	Maintaining a neutral and attentive facial expression

DISTURBANCE AT THE VOTE CENTER

If any person is unruly, abusive, or threatens the safety of the Election Worker, Voter, or the orderly conduct of the election in any way, call 911 immediately followed up with a call to the Registrar of Voters' Office Election Worker Hotline (510) 835-7205.

The Registrar of Voters works closely with local law enforcement agencies who have been given location details of all the Vote Centers and 24-Hour Drop Boxes and will respond quickly to any issues.

ARTIFICIAL INTELLIGENCE CAPABILITIES & CONSIDERATIONS

Artificial intelligence technology has created new challenges for Election Workers to consider. Bad actors can fake audio, video, or writing to mimic the voice, likeness, or writing style of public elections officials. Election Workers should call the county elections office to verify instructions that are out of the ordinary.

CHALLENGING A VOTER'S RIGHT TO VOTE

Per law, Election Workers may challenge a Voter's right to vote in the Vote Center. For additional questions about challenge procedures, contact the Election Worker Hotline immediately at (510) 835-7205.

REPORTING VOTER FRAUD

If Voter wants to report suspected fraud, provide the Voter with a Voter Fraud Telephone Card, so the Voter can contact the California Secretary of State at (916) 657-2166.

LAW ENFORCEMENT OFFICERS AT THE VOTE CENTER

There are rules related to when law enforcement officers are permitted at Vote Centers.

If law enforcement officers enter the Vote Center, call the Election Worker Hotline at (510) 835-7205.

EMERGENCY SITUATIONS

The safety of Election Workers and voters is the first priority in an emergency on Election Day. The second priority is the security of the voted ballots and the voting materials. Emergencies include (but are not limited to): earthquakes, fire or explosions, armed assailant(s), flooding, hazardous substances and chemical spills, bomb threats, and emotionally disturbed persons. The following information is intended to be a general guide when making decisions regarding the election process during an emergency. Call 911 first, and then notify the Election Worker Hotline as soon as possible.

IF AN EMERGENCY REQUIRES EVACUATION

Evacuate voters in the Vote Center immediately. If safe to do so, bring the following items:

- All voted ballots,
- Poll Pad(s),
- Unused ballots,
- Lime Bag,
- Turquoise Official Ballots Bag,
- Yellow Vote by Mail Ballots Trolley,
- Blue Provisional Ballots Trolley, and
- Unused Provisional Envelopes

In the case that these items were not able to be brought out and voting has stopped at this location, first ensure the safety of all Election Workers and Voters, then communicate with the Election Worker Hotline at (510) 835-7205. Post a sign at the entrance of the Vote Center stating that the site has closed and direct voters to the nearest Vote Center(s). When time allows, contact the Election Worker Hotline at (510) 835-7205 to update them on the current situation. Resume voting as soon as possible when the building is reopened or the Vote Center is moved to a safe location.

SEE SOMETHING, SAY SOMETHING

If you notice any activity that seems unusual or may not align with election procedures, please contact Election Worker Recruiting:


- Call (510) 272-6971 or
- Email rov_pollworker_info@acgov.org

Providing clear details will help us review the situation appropriately. All reports are handled appropriately to maintain the integrity of the process. If you receive additional guidance from the Registrar of Voters, please follow those instructions.

ROVER PROCEDURE

ROVER PROCEDURE

ROVER PREPARATION



- Rovers will be wearing a **Blue Vest** and **Rover badge**.
- First afternoon Rover Pick Up begins at **3:00 PM*** on **Election Day ONLY**.
** Time may vary depending on Rover Pick Up route.*
- **PREPARE** the following for Pick Up:

YELLOW VOTE BY MAIL BALLOTS TROLLEY



1. **CLOSE & SEAL** the deposit slot on Trolley with a White Security Seal. Then **SET ASIDE** for Rover.



2. **REPLACE** Yellow Vote by Mail Ballots Trolley with another Yellow Vote by Mail Ballots Trolley by 3:00 PM on Election Day.
3. **PERFORM 1ST VOTER PROCEDURE*** for the replacement Yellow Vote by Mail Ballots Trolley.
** As required by the California Secretary of State, the first Voter to vote after the replacement Trolley is set up must verify the Trolley is empty.*

TURQUOISE OFFICIAL BALLOTS BAG

NOTE: CHECK inside the Voting booths, and Secrecy Sleeves for any hidden ballots.

2 PERSON RULE



Captain



Assistant
Captain



1. **CLOSE & SEAL** the deposit slot on Bag with a White Security Seal. Then **SET ASIDE** for Rover.



2. **ROVER SCANS** the Turquoise Official Ballots Bag.




3. **REPLACE** Turquoise Official Ballots Bag with another Turquoise Official Ballots Bag by 3:00 PM on Election Day.
4. **PERFORM 1ST VOTER PROCEDURE*** for the Turquoise Official Ballots Bag and Bin.
**As required by the California Secretary of State, the first Voter to vote after the replacement Bag is set up must verify the Bag is empty.*

CLOSING

CLOSING

CLOSING — SUPPLY CHAIN



1. **USE** the Supply Chain diagram to assist in finding where supplies should be placed during Closing Polls.

NOTE: This page is a representation of the Supply Chain document, which is located in the Captain Supply Box.

TASK 1 ANNOUNCE CLOSING OF THE POLLS

DAILY

DAILY

DAILY

DAILY

DAILY

At the scheduled closing time, **STEP OUTSIDE & MAKE THE ANNOUNCEMENT:**

“THE VOTE CENTER IS NOW CLOSED!”

NOTE FOR ELECTION NIGHT AT 8 PM:

IF THERE IS A LINE OF VOTERS OUTSIDE WAITING TO VOTE, INFORM A DEMONSTRATION OFFICER to stand at the end of the line by the time of closing. The Demonstration Officer will inform Voters who arrive after the Polls are closed that they will not be allowed to vote.

If VBM Voter, who is not in line by 8 PM, submits a VBM Ballot, WRITE "TOO LATE" on envelope then PLACE into Lime Bag.

TASK 2 CLOSING ROVER PICK UP

TWO (2) PERSON RULE

DAILY

DAILY

DAILY

DAILY

DAILY

NOTE: CHECK inside the Voting booths, and Secrecy Sleeves for any hidden ballots.

2 PERSON RULE

Any two (2) Election Workers



- 1. CLOSE & SEAL** the deposit slot on Bag with a White Security Seal. Then **SET ASIDE** for Rover.

NOTE: If there are any voted Vote Center Ballots in the Teal Unscanned Voted Ballots Bag, **PLACE** entire bag into the Turquoise Official Ballots Bag. **SEAL** the Turquoise Official Ballots Bag with a white security seal.



2. **ROVER SCANS** the Turquoise Official Ballots Bag.

DAILY

DAILY

DAILY

DAILY

DAILY



3. **SLIDE UP** the tab below the opening of the Deposit Slot of both the Yellow Vote by Mail Ballots Trolley and the Blue Provisional Ballots Trolley to close and secure. **PLACE** White Security Seal on both the Yellow and Blue Trolleys' Ballot Deposit Slot, as shown above. The White Security Seal must pass through both the small opening on the bottom edge of the Deposit Slot and the opening of the tab.
4. **GIVE ROVER** the following items:
 - Turquoise Official Ballots Bag
 - Yellow Vote by Mail Ballots & Blue Provisional Ballots Trolley




TASK 3 SEAL OFFICIAL VOTE CENTER BALLOTS

ELECTION NIGHT

ELECTION NIGHT

ELECTION NIGHT

ELECTION NIGHT



1. Only at the end of Election Night, **PLACE** an Unused Official Ballots Box Seal on the opened Official Vote Center Ballots boxes **only**. Captain and three (3) other Election Workers must sign the seal.
2. Opened and unopened Official Vote Center Ballots boxes must stay in its Official Ballots Delivery Cart(s). **SEAL** the Official Ballots Delivery Cart(s) containing the Official Vote Center Ballots boxes when finished.

TASK 4 CLOSING POLL PAD


DAILY

DAILY


DAILY

DAILY


DAILY




1. **POWER OFF** the printer by switching ON/OFF switch to the OFF position.




2. **DISCONNECT** the power cable from the back of the printer and the surge protector. **PLACE** the power cable then the printer inside the carrying case, which is located in the Official Ballots Delivery Cart.



3. **DISCONNECT** the stand from the Poll Pad. **SEPARATE** the stand arm of the stand from the base then **FOLD** the stand arm to fit in the carrying case.




4. **ENSURE** Poll Pad screen is not locked. The Poll Pad will synchronize. **MAKE SURE** the cloud icon is green and the Poll Pad is connected to the WiFi. **PRESS** the cloud icon to confirm that the synchronization is finished.



5. **TURN OFF** Poll Pad by holding the power button. Screen will ask to "swipe/slide" to confirm powering off. **DISCONNECT** the charger from the Poll Pad.

NOTE: DO NOT POWER OFF until 30 minutes after the last Voter has been processed.



6. **PLACE** the Poll Pad inside the lid of the carrying case and use the velcro strap to secure. **RETURN** any remaining designated supplies to the Poll Pad case. **CLOSE** the lid and **SECURE**.
7. **PLACE** Poll Pad case in the Official Ballots Delivery Cart.

TASK 5 PACK CRADLEPOINT ROUTER

DAILY

DAILY

DAILY

DAILY

DAILY

NOTE: DO NOT POWER OFF until 30 minutes after the last Voter has been processed.




1. After the Poll Pads have finished syncing, on the back of the Cradlepoint, **FLIP** the power switch downward to the OFF position. **REMOVE** power cord from the back of the Cradlepoint and the power source.

NOTE: **PRESS** on the bottom tab of the connector while removing the power cord (as seen in the photo).



2. **UNSCREW** the antennas from the back of the Cradlepoint. **RETRIEVE** the Cradlepoint case and **PLACE** the antennas and power cord in the case.
3. **PLACE** the Cradlepoint case back in the Official Ballots Delivery Cart.





1. **SHUT DOWN** the laptop by clicking the Start menu and locating the power icon. **CLICK** on the power icon and select “Shut Down.”
2. When the screen turns off, **CLOSE** the Laptop and **SAFELY DISCONNECT** the power cable and USB cable.
3. **PULL OUT** the cart’s bottom rolling drawer. **REMOVE** the empty laptop cardboard box and safely insert the laptop inside the cardboard box. **PLACE** it back in the bottom rolling drawer.
4. **SECURE** the laptop using the straps.
5. **STRAP** the printer’s back Velcro straps together.
6. **POWER OFF** the BOD printer by holding down the white power button located on the right side of the printer’s LCD.
7. **FLIP BACK** the laptop’s top compartment and use the Cart’s key to close it by turning the key Clockwise.
8. **SLIDE** the laptop’s top compartment shelf to the right by removing both of the shelf locks (underneath the shelf, one in the front of shelf and the other on backside of the shelf) and **SLIDE** it back in place.
9. **USE** a White Security Seal to secure the top compartment’s laptop and the safety latch.
10. **SAFELY DISCONNECT** the BOD’s black power cable from the connected power source. **STORE** the cart’s black power cable back inside the cart’s rolling drawer.
11. **CLOSE** the cart’s front door by inserting the key into the lock and turning it counterclockwise.
12. **USE** White Security Seals to seal the cart’s front door.
13. **PLACE** the Cart’s Key back in the phone pouch.

[illegible][illegible]

- 14. COUNT & FILL OUT** "End of day Total" on the "Finished Ballot Card Log" and the "Damage Ballot Inventory Control Log" sheets in the BOD Audit Binder, then **PLACE** the Binder in the Captain Supply Box.

TASK 7 SHUT DOWN VIG ON DEMAND


DAILY

DAILY


DAILY

DAILY



DAILY



1. **POWER OFF** the VIG On Demand Printer by pressing and holding the power button on top of the Printer. **SHUT DOWN** the VIG On Demand Laptop.



2. **DISCONNECT** the all USB cables from the Printer and the Laptop once powered off. **DISCONNECT** the Laptop charger cable from the Laptop.



3. **DISCONNECT** the Laptop charger and Printer power cables from the surge protector.
4. Separately **PLACE** each of the VIG On Demand equipment back into the plastic bags, then **PLACE** into the carrying case.
5. **CLOSE** carrying case and **PLACE** in the Official Ballot Delivery Cart.

NOTE: Firmly press on the latches on the case to securely close.

TASK 8 CLOSING BALLOT MARKING TOUCHSCREENS*

TWO (2) PERSON RULE

DAILY

DAILY

DAILY

DAILY

DAILY

CLOSE POLLS on Ballot Marking Touchscreens.

**Refer to Ballot Marking Touchscreen Closing Section for instructions on pg. 189*

TASK 9 PACK ITEMS IN COLORED BAGS

DAILY

DAILY

DAILY

DAILY

DAILY

1. **PLACE** the following bags in the Official Ballots Delivery Cart:



All Ballots Bags must be stored in the Official Ballots Delivery Cart, daily.

If there are any voted Vote Center Ballots in the Teal Unscanned Voted Ballots Bag, PLACE the entire bag into the Turquoise Official Ballots Bag. **SEAL** the Turquoise Official Ballots Bag with a White Security Seal (refer to pg. 166)

TASK 10 PACK ITEMS IN LIME BAG


ELECTION NIGHT

ELECTION NIGHT


ELECTION NIGHT

ELECTION NIGHT

NOTE: Any VBM Envelopes that are submitted after 8 PM on Election Day must be marked "TOO LATE" then placed into the Lime Bag.



1. Once all items are inside Lime Bag, **SEAL** Deposit Slot with White Security Seal (see image on right).
2. **PLACE** the Lime Bag in the Official Ballots Delivery Cart.



CLOSING

TASK 11 PACK ITEMS ON OFFICIAL TABLE

ELECTION NIGHT

ELECTION NIGHT

ELECTION NIGHT

ELECTION NIGHT

1. PACK remaining items into Official Table Supply Box:



- ATI Earphone Covers
- Binder Clips
- Election Worker Digest
- Extra Poll Pad paper
- Accessible Supplies (Magnifier and Pen with Grip, Signature Guides, Magnifying Glass)
- Secrecy Sleeves
- Voter Fraud Telephone Cards
- I Voted Stickers

2. PLACE the Official Table Supply Box in the Official Ballots Delivery Cart.

TASK 12 PACK OPENING POLLS SUPPLY BOX


ELECTION NIGHT

ELECTION NIGHT

ELECTION NIGHT

ELECTION NIGHT

1. PACK the smaller Inside and Outside Signs in the Opening Supply Box.



NOTE: All Outside Signs must be stored within the Vote Center, daily.

TASK 12 PACK OPENING POLLS SUPPLY BOX

ELECTION NIGHT

ELECTION NIGHT

ELECTION NIGHT

ELECTION NIGHT

2. **PACK** the following remaining items from the Official Table in the Opening Polls Supply Box:



3. **PLACE** the Opening Polls Supply Box in the Official Ballots Delivery Cart.



TASK 13 PACK ELECTRICAL SUPPLY BOX


ELECTION NIGHT

ELECTION NIGHT

ELECTION NIGHT

ELECTION NIGHT

1. **PACK** all provided electrical cables into the Electrical Supply Box.



2. **PLACE** the Electrical Supply Box in the Official Ballots Delivery Cart.



1. PLACE the following in the Captain Supply Box:


HAVA ID REQUIREMENTS BINDER

[illegible]

TOUCHSCREEN DAILY LOG SHEET

[illegible]

SECURITY SEALS ENVELOPE



SEAL VERIFICATION FORMS

[illegible]

BREAK SCHEDULES

[illegible]


VOTE CENTER BALLOT INDEX

#	Ballot Type	Language	Card Count	Box Number
Ballot Type - 1				
1	1	Chinese	1	1-1000
2	1	Spanish	1	1-1000
3	1	Tagalog	1	1-1000
4	1	Vietnamese	1	1-1000
Ballot Type - 2				
1	2	Chinese	1	1-1000
2	2	Spanish	1	1-1000
3	2	Tagalog	1	1-1000
4	2	Vietnamese	1	1-1000
Ballot Type - 3				
1	3	Chinese	1	1-1000
2	3	Spanish	1	1-1000
3	3	Tagalog	1	1-1000
4	3	Vietnamese	1	1-1000
Ballot Type - 4				
1	4	Chinese	1	1-1000
2	4	Spanish	1	1-1000
3	4	Tagalog	1	1-1000
4	4	Vietnamese	1	1-1000
Ballot Type - 5				
1	5	Chinese	1	2-1000
2	5	Spanish	1	2-1000
3	5	Tagalog	1	2-1000
4	5	Vietnamese	1	2-1000

BALLOT ON DEMAND AUDIT BINDER



SUPPLY CHAIN



CELL PHONE WITH TOUCHSCREEN POLL WORKER CARDS



ADDITIONAL ITEMS:

- **EXTRA ELECTION PINS**
- **EXTRA ELECTION WORKER GUIDES**
- **OFFICIAL WRITE-IN CANDIDATES LIST** *(if applicable)*
- **BOD PRINTER CART KEYS W/ LUGGAGE TAG**



- EXTRA UNUSED OFFICIAL BALLOTS BOX SEALS
- EXTRA VOTED OFFICIAL BALLOTS BOX SEALS
- LANGUAGE HOTLINE SIGN
- LANGUAGE COLOR GUIDE SIGN

2. PLACE the Captain Supply Box in the Official Ballots Delivery Cart.

TASK 15 STORE & SEAL SUPPLIES

1. **PLACE** the following into the Official Ballots Delivery Cart:

DAILY STORAGE ITEMS

UNUSED REPLACEMENT
VOTE BY MAIL ENVELOPESUNUSED CONDITIONAL PROVISIONAL
REGISTRATION FORMSUNUSED VOTER
REGISTRATION
FORMSUNINTERRUPTIBLE POWER
SUPPLY (UPS)

ADDITIONAL ITEMS:

- CRADLEPOINT WIFI ROUTER
- VIG ON DEMAND CASE
- BALLOT MARKING TOUCHSCREEN & PRINTER CASES
- UNUSED OFFICIAL VOTE CENTER BALLOTS
- EXTRA TOUCHSCREEN BALLOT PAPER
- EXTRA BOD PAPER
- LIME BAG
- OPENING POLLS SUPPLY BOX
- CAPTAIN SUPPLY BOX
- ELECTRICAL SUPPLY BOX
- GRAY VOIDED/ SURRENDERED VOTE BY MAIL BALLOTS
- PURPLE SPOILED BALLOTS
- TEAL UNSCANNED VOTED BALLOTS BAGS
- YELLOW VOTE BY MAIL BALLOTS TROLLEY
- BLUE PROVISIONAL BALLOTS TROLLEY
- TURQUOISE OFFICIAL BALLOTS BAG

ELECTION NIGHT ITEMS

- EXTRA STATE & ALAMEDA COUNTY VOTER INFORMATION GUIDES
- TRASH BAGS & STAND
- TABLE CLOTHS

2. **PLACE** White Security Seals on Official Ballots Delivery Carts' doors, then **PLACE** one through the zipper and lower-bottom loops of the Cart to seal all equipment (*see image on right*).



TASK 16 DISMANTLE BLUE VOTING BOOTHS


ELECTION NIGHT

ELECTION NIGHT


ELECTION NIGHT

ELECTION NIGHT


CLOSING



1. **LEAVE** all signs posted inside Voting Booth. From inside the booth, **DETACH** Privacy Shield by pulling bungee cords through slits in Shield then **FOLD** together.



2. **TURN** booth upside down and **DETACH** legs from booth. **PULL** apart each of the legs to reduce the size.



3. **PLACE** Privacy Shields and legs into the inside of the Voting Booth.


TASK 16 DISMANTLE BLUE VOTING BOOTHS

ELECTION NIGHT


ELECTION NIGHT

ELECTION NIGHT


ELECTION NIGHT



4. **HOOK** S-hook to secure legs and Shield.



5. **LATCH** two (2) booths together and stack on the Supply Delivery Box.



FOR ACCESSIBLE VOTING BOOTHS:

UNLOCK Adapter by lifting the locking tab upwards. **PLACE** Adapters in the Opening Polls Supply Box.

TASK 17 DISMANTLE TOUCHSCREEN VOTING BOOTHS

ELECTION NIGHT

ELECTION NIGHT

ELECTION NIGHT

ELECTION NIGHT



1. **DETACH** “Scroll Up/Down” sign from the front left vertical support. **PLACE** the sign the Opening Polls Supply Box.

TASK 17 DISMANTLE TOUCHSCREEN VOTING BOOTHS


ELECTION NIGHT

ELECTION NIGHT


ELECTION NIGHT

ELECTION NIGHT


CLOSING



2. From underneath the table, **SLIDE** latch to lock and secure.



3. Carefully **LOWER** table down, aligning the table with the back portion of the booth.



4. **FOLD** the Touchscreen Voting Booth together with the Velcro strap facing out. **ATTACH** velcro strap together to secure. **PLACE** the booth in the Supply Deliver Box.

TASK 18 PACK LARGE SIGNAGE

ELECTION NIGHT

ELECTION NIGHT


ELECTION NIGHT

ELECTION NIGHT

1. **TAKE DOWN & DISMANTLE** the bigger Inside and Outside Signs. **PLACE** the poster signs into the designated tubes.



NOTE: All Outside Signs must be stored within the Vote Center, daily.



2. **FOLD** together the Tri-fold displays.



3. **RETURN** all Signs and Booths to the Supply Delivery Boxes.
If space inside the Supply Delivery Box has limited space, **PLACE** remaining items beside it.


ASSIST OTHER ELECTION WORKERS WITH TASKS, IF FINISHED EARLY.

BALLOT MARKING TOUCHSCREEN CLOSING

BALLOT MARKING TOUCHSCREEN CLOSING



1. **INSERT** the Poll Worker Card into the Ballot Marking Touchscreen. **PRESS** "Log in" on the upper left of the menu. **ENTER** the Administrator Login number, then **PRESS** the "Login" button.




2. **PRESS** the "Close Poll" button, then **PRESS** "Yes" button to confirm closing the Poll.

TOUCHSCREEN DAILY LOG SHEET
 COUNTY OF ALAMEDA
 JUNE 16, 2026 CONGRESSIONAL DISTRICT 14, SPECIAL PRIMARY ELECTION
 VOTE CENTER #: 1
 LOCATION: FAITH LUTHERAN CHURCH
 ADDRESS: 20080 REDWOOD RD CASTRO VALLEY

IMPORTANT: CALIFORNIA SECRETARY OF STATE GUIDELINES REQUIRE (2) ELECTION WORKERS PERFORM THE FOLLOWING PROCEDURES.

TOUCHSCREEN	TOTAL BALLOTS PRINTED	DATE	ELECTION WORKER NAME	SIGNATURE
		JUNE 6, 2026	#1	
			#2	
		JUNE 7, 2026	#1	
			#2	
		JUNE 8, 2026	#1	
			#2	
		JUNE 9, 2026	#1	
			#2	
		JUNE 10, 2026	#1	
			#2	
		JUNE 11, 2026	#1	
			#2	
		JUNE 12, 2026	#1	
			#2	
		JUNE 13, 2026	#1	
			#2	
		JUNE 14, 2026	#1	
			#2	
		JUNE 15, 2026	#1	
			#2	
		JUNE 16, 2026	#1	
			#2	

3. **FILL OUT** the Touchscreen Daily Log Sheet accordingly (located in the Captain Supply Box).



4. **PRESS** the "Reset counters" button by Public Counter (**only Early Voting, not applicable to Election Day closing**), then **PRESS** "Yes" button to confirm.


DAILY

DAILY


DAILY

DAILY

DAILY




5. **ENTER** the Administrator Login number, then **PRESS** the “Confirm” button.




6. **PRESS** the “Power off” button on the bottom-right corner. Then **SELECT** the “Power off” button option to shut off the Ballot Marking Touchscreen.




7. **REMOVE** the Poll Worker Card then **PLACE** inside Cell Phone pouch.



1. **PRESS & HOLD** the Power button on the front side of the Printer to power off.



2. **DISCONNECT** both Printer power cord and Printer cable from the back of the Printer.



3. **DISCONNECT** the Ballot Marking Touchscreen power cord from the base of the Ballot Marking Touchscreen.
4. **DISCONNECT** both Printer and Ballot Marking Touchscreen power cords from the surge protector.


DAILY

DAILY

DAILY


DAILY

DAILY




1. **RETRIEVE** the Printer case and place flat on a surface with the rolling handle on the bottom. **UNZIP & OPEN** the case.
2. **PLACE** the Printer in the Printer case using the handle on the side.

NOTE: POSITION the printer so the back faces the bottom of the carrying case.




3. **FOLD & PLACE** the power cord and Printer cable in the Printer case. **SECURE** the Velcro strap around the Printer.
4. **CLOSE** the case, **STAND** upright, and **PLACE** back into the Official Ballots Delivery Cart.



1. **RETRIEVE** the Ballot Marking Touchscreen case and place flat on a surface. **UNZIP** and open the case. **RETRIEVE** the small box within and **PLACE** the Touchscreen power cable inside.
2. **LIFT** the Ballot Marking Touchscreen up using the handle behind the screen. **PLACE** protective packaging on the Ballot Marking Touchscreen.

NOTE: DO NOT DISCONNECT OR REMOVE ANY CABLES connected to the Audio Tactile Interface (ATI) when closing the Ballot Marking Touchscreen.



3. **PLACE** the Touchscreen in the Ballot Marking Touchscreen case. Without removing any cables, **PLACE** the ATI with headphones in its bubble wrap between the protective packaging and the small box containing the power cable on top, inside the Ballot Marking Touchscreen case.

4. **CLOSE** the case, **STAND** upright, then **PLACE** back into the Official Ballots Delivery Cart. **SEAL** the Official Ballots Delivery Cart when finished.

MY POLL WORKER PROFILE

All Election Worker materials and resources are available by accessing the link under the **My Poll Worker Profile** at pollworker.acgov.org

BILINGUAL ELECTION WORKERS

- As a Bilingual Election Worker, you are required to **take and pass** a Mandatory Bilingual Online Training prior to Election Day.
- **Bilingual Online Training** can be accessed through:
My Poll Worker Profile: <http://pollworker.acgov.org>
- Additional computer labs are available at our training sites for access to Bilingual Online Training.
- **If you have any questions about the Bilingual Online Training**, please call **(510) 272-6971** or email at rov_pollworker@acgov.org

ELECTION WORKER QUESTIONS

For Election Worker questions:

- Email ROV Recruiting at rov_pollworker_info@acgov.org or;
- Call **(510) 272-6971**

My Poll Worker Profile can now be accessed online by visiting pollworker.acgov.org



NOTES

[illegible]

NOTES

Thank You!

Your efforts to serve the Voters of Alameda County are sincerely appreciated!

ACVOTE



FOR VOTER ASSISTANCE, CALL:

ENGLISH:	(510) 272-6973	CHINESE:	(510) 208-9665
SPANISH:	(510) 272-6975	TAGALOG:	(510) 272-6952
VIETNAMESE:	(510) 272-6956	BENGALI:	(510) 208-0931
BURMESE:	(510) 208-0925	HINDI:	(510) 272-5035
JAPANESE:	(510) 272-5036	KHMER:	(510) 272-5038
KOREAN:	(510) 272-5037	LAOTIAN:	(510) 208-0926
MALAY:	(510) 208-0933	MIEN:	(510) 208-0927
MONGOLIAN:	(510) 208-0928	PUNJABI:	(510) 272-5035
TELUGU:	(510) 208-0929	URDU:	(510) 208-0932